

# Reactor Netty Reference Guide

Stephane Maldini, Violeta Georgieva

Version 1.1.0

# Table of Contents

1. About the Documentation .....	1
1.1. Latest Version and Copyright Notice .....	1
1.2. Contributing to the Documentation .....	1
1.3. Getting Help .....	1
2. Getting Started .....	2
2.1. Introducing Reactor Netty .....	2
2.2. Prerequisites .....	2
2.3. Understanding the BOM and versioning scheme .....	2
2.4. Getting Reactor Netty .....	3
2.5. Support and policies .....	6
3. TCP Server .....	8
3.1. Starting and Stopping .....	8
3.2. Eager Initialization .....	10
3.3. Writing Data .....	11
3.4. Consuming Data .....	12
3.5. Lifecycle Callbacks .....	13
3.6. TCP-level Configurations .....	14
3.7. SSL and TLS .....	21
3.8. Metrics .....	23
3.9. Tracing .....	26
3.10. Unix Domain Sockets .....	29
4. TCP Client .....	31
4.1. Connect and Disconnect .....	31
4.2. Eager Initialization .....	32
4.3. Writing Data .....	33
4.4. Consuming Data .....	35
4.5. Lifecycle Callbacks .....	37
4.6. TCP-level Configurations .....	38
4.7. Connection Pool .....	45
4.8. SSL and TLS .....	50
4.9. Proxy Support .....	52
4.10. Metrics .....	53
4.11. Tracing .....	57
4.12. Unix Domain Sockets .....	60
4.13. Host Name Resolution .....	60
5. HTTP Server .....	64
5.1. Starting and Stopping .....	64
5.2. Eager Initialization .....	66

5.3. Routing HTTP	67
5.4. Writing Data	71
5.5. Consuming Data	73
5.6. Lifecycle Callbacks	82
5.7. TCP-level Configuration	83
5.8. SSL and TLS	88
5.9. HTTP Access Log	90
5.10. HTTP/2	93
5.11. Metrics	96
5.12. Tracing	101
5.13. Unix Domain Sockets	104
6. HTTP Client	106
6.1. Connect	106
6.2. Eager Initialization	108
6.3. Writing Data	109
6.4. Consuming Data	113
6.5. Lifecycle Callbacks	117
6.6. TCP-level Configuration	119
6.7. Connection Pool	124
6.8. SSL and TLS	132
6.9. Retry Strategies	134
6.10. HTTP/2	134
6.11. Proxy Support	137
6.12. Metrics	138
6.13. Tracing	143
6.14. Unix Domain Sockets	147
6.15. Host Name Resolution	148
6.16. Timeout Configuration	151
7. UDP Server	162
7.1. Starting and Stopping	162
7.2. Eager Initialization	163
7.3. Writing Data	164
7.4. Consuming Data	165
7.5. Lifecycle Callbacks	166
7.6. Connection Configuration	167
7.7. Metrics	174
7.8. Unix Domain Sockets	177
8. UDP Client	179
8.1. Connecting and Disconnecting	179
8.2. Eager Initialization	180
8.3. Writing Data	181

8.4. Consuming Data .....	182
8.5. Lifecycle Callbacks .....	183
8.6. Connection Configuration .....	184
8.7. Metrics .....	191
8.8. Unix Domain Sockets .....	194
Appendix A: Frequently Asked Questions .....	196
A.1. Connection to the proxy cannot be established .....	196
A.2. What is it meaning of the information that is prepended to every log record? .....	196
A.3. How can I extract all log records for a particular HTTP request? .....	198
A.4. How can I debug a memory leak? .....	198
A.5. How can I debug "Connection prematurely closed BEFORE response"? .....	198
Appendix B: Observability .....	200
B.1. Observability metadata .....	200

# Chapter 1. About the Documentation

This section provides a brief overview of **Reactor Netty** reference documentation. You do not need to read this guide in a linear fashion. Each piece stands on its own, though they often refer to other pieces.

## 1.1. Latest Version and Copyright Notice

The **Reactor Netty** reference guide is available as **HTML** documents. The latest copy is available at <https://projectreactor.io/docs/netty/release/reference/index.html>

Copies of this document may be made for your own use and for distribution to others, provided that you do not charge any fee for such copies and further provided that each copy contains this **Copyright Notice**, whether distributed in print or electronically.

## 1.2. Contributing to the Documentation

The reference guide is written in **AsciiDoc**, and you can find its sources at <https://github.com/reactor/reactor-netty/tree/main/docs/asciidoc>.

If you have an improvement, we will be happy to get a pull request from you!

We recommend that you check out a local copy of the repository so that you can generate the documentation by using the **asciidocctor** Gradle task and checking the rendering. Some of the sections rely on included files, so **GitHub** rendering is not always complete.

## 1.3. Getting Help

There are several ways to reach out for help with **Reactor Netty**. You can:

- Get in touch with the community on [Gitter](#).
- Ask a question on stackoverflow.com at [reactor-netty](#).
- Report bugs in **GitHub** issues. The repository is the following: [reactor-netty](#).



All of **Reactor Netty** is open source, [including this documentation](#).

# Chapter 2. Getting Started

This section contains information that should help you get going with **Reactor Netty**. It includes the following information:

- [Introducing Reactor Netty](#)
- [Prerequisites](#)
- [Understanding the BOM and versioning scheme](#)
- [Getting Reactor Netty](#)

## 2.1. Introducing Reactor Netty

Suited for Microservices Architecture, **Reactor Netty** offers backpressure-ready network engines for **HTTP** (including Websockets), **TCP**, and **UDP**.

## 2.2. Prerequisites

**Reactor Netty** runs on **Java 8** and above.

It has transitive dependencies on:

- Reactive Streams v1.0.4
- Reactor Core v3.x
- Netty v4.1.x

## 2.3. Understanding the BOM and versioning scheme

**Reactor Netty** is part of the **Project Reactor BOM** (since the **Aluminium** release train). This curated list groups artifacts that are meant to work well together, providing the relevant versions despite potentially divergent versioning schemes in these artifacts.



The versioning scheme has changed between 0.9.x and 1.0.x (Dysprosium and Europium).

Artifacts follow a versioning scheme of **MAJOR.MINOR.PATCH-QUALIFIER** while the BOM is versioned using a CalVer inspired scheme of **YYYY.MINOR.PATCH-QUALIFIER**, where:

- **MAJOR** is the current generation of Reactor, where each new generation can bring fundamental changes to the structure of the project (which might imply a more significant migration effort)
- **YYYY** is the year of the first GA release in a given release cycle (like 1.0.0 for 1.0.x)
- **.MINOR** is a 0-based number incrementing with each new release cycle
  - in the case of projects, it generally reflects wider changes and can indicate a moderate migration effort
  - in the case of the BOM it allows discerning between release cycles in case two get first

released the same year

- **.PATCH** is a 0-based number incrementing with each service release
- **-QUALIFIER** is a textual qualifier, which is omitted in the case of GA releases (see below)

The first release cycle to follow that convention is thus **2020.0.x**, codename **Europium**. The scheme uses the following qualifiers (note the use of dash separator), in order:

- **-M1..-M9**: milestones (we don't expect more than 9 per service release)
- **-RC1..-RC9**: release candidates (we don't expect more than 9 per service release)
- **-SNAPSHOT**: snapshots
- *no qualifier* for GA releases



Snapshots appear higher in the order above because, conceptually, they're always "the freshest pre-release" of any given PATCH. Even though the first deployed artifact of a PATCH cycle will always be a -SNAPSHOT, a similarly named but more up-to-date snapshot would also get released after eg. a milestone or between release candidates.

Each release cycle is also given a codename, in continuity with the previous codename-based scheme, which can be used to reference it more informally (like in discussions, blog posts, etc...). The codenames represent what would traditionally be the MAJOR.MINOR number. They (mostly) come from the [Periodic Table of Elements](#), in increasing alphabetical order.



Up until Dysprosium, the BOM was versioned using a release train scheme with a codename followed by a qualifier, and the qualifiers were slightly different. For example: Aluminium-RELEASE (first GA release, would now be something like YYYY.0.0), Bismuth-M1, Californium-SR1 (service release would now be something like YYYY.0.1), Dysprosium-RC1, Dysprosium-BUILD-SNAPSHOT (after each patch, we'd go back to the same snapshot version. would now be something like YYYY.0.X-SNAPSHOT so we get 1 snapshot per PATCH)

## 2.4. Getting Reactor Netty

As [mentioned earlier](#), the easiest way to use **Reactor Netty** in your core is to use the **BOM** and add the relevant dependencies to your project. Note that, when adding such a dependency, you must omit the version so that the version gets picked up from the **BOM**.

However, if you want to force the use of a specific artifact's version, you can specify it when adding your dependency as you usually would. You can also forego the **BOM** entirely and specify dependencies by their artifact versions.

### 2.4.1. Maven Installation

The **BOM** concept is natively supported by **Maven**. First, you need to import the **BOM** by adding the following snippet to your **pom.xml**. If the top section (**dependencyManagement**) already exists in your pom, add only the contents.

```

<dependencyManagement> ①
  <dependencies>
    <dependency>
      <groupId>io.projectreactor</groupId>
      <artifactId>reactor-bom</artifactId>
      <version>2022.0.0</version> ②
      <type>pom</type>
      <scope>import</scope>
    </dependency>
  </dependencies>
</dependencyManagement>

```

① Notice the `dependencyManagement` tag. This is in addition to the regular `dependencies` section.

② As of this writing, `2022.0.0` is the latest version of the `BOM`. Check for updates at <https://github.com/reactor/reactor/releases>.

Next, add your dependencies to the relevant reactor projects, as usual (except without a `<version>`). The following listing shows how to do so:

```

<dependencies>
  <dependency>
    <groupId>io.projectreactor.netty</groupId>
    <artifactId>reactor-netty-core</artifactId> ①
  </dependency> ②
</dependencies>
<dependencies>
  <dependency>
    <groupId>io.projectreactor.netty</groupId>
    <artifactId>reactor-netty-http</artifactId>
  </dependency>
</dependencies>

```

① Dependency on `Reactor Netty`

② No version tag here

## 2.4.2. Gradle Installation

The `BOM` concept is supported in Gradle since version 5. The following listing shows how to import the `BOM` and add a dependency to `Reactor Netty`:



```
dependencies {
    // import a BOM
    implementation platform('io.projectreactor:reactor-bom:2022.0.0') ①

    // define dependencies without versions
    implementation 'io.projectreactor.netty:reactor-netty-core' ②
    implementation 'io.projectreactor.netty:reactor-netty-http'
}
```

① As of this writing, 2022.0.0 is the latest version of the BOM. Check for updates at <https://github.com/reactor/reactor/releases>.

② There is no third : separated section for the version. It is taken from the BOM.

### 2.4.3. Milestones and Snapshots

Milestones and developer previews are distributed through the **Spring Milestones** repository rather than **Maven Central**. To add it to your build configuration file, use the following snippet:

#### *Milestones in Maven*

```
<repositories>
  <repository>
    <id>spring-milestones</id>
    <name>Spring Milestones Repository</name>
    <url>https://repo.spring.io/milestone</url>
  </repository>
</repositories>
```

For Gradle, use the following snippet:

#### *Milestones in Gradle*

```
repositories {
    maven { url 'https://repo.spring.io/milestone' }
    mavenCentral()
}
```

Similarly, snapshots are also available in a separate dedicated repository (for both Maven and Gradle):

-SNAPSHOTS in Maven

```
<repositories>
  <repository>
    <id>spring-snapshots</id>
    <name>Spring Snapshot Repository</name>
    <url>https://repo.spring.io/snapshot</url>
  </repository>
</repositories>
```

-SNAPSHOTS in Gradle

```
repositories {
  maven { url 'https://repo.spring.io/snapshot' }
  mavenCentral()
}
```

## 2.5. Support and policies

The entries below are mirroring <https://github.com/reactor/.github/blob/main/SUPPORT.adoc>

### 2.5.1. Do you have a question?



Search Stack Overflow first; discuss if necessary

If you're unsure why something isn't working or wondering if there is a better way of doing it please check on **Stack Overflow** first and if necessary start a discussion. Use relevant tags among the ones we monitor for that purpose:

- **reactor-netty** for specific reactor-netty questions
- **project-reactor** for generic reactor questions

If you prefer real-time discussion, we also have a few **Gitter channels**:

- **reactor** is the historic most active one, where most of the community can help
- **reactor-core** is intended for more advanced pinpointed discussions around the inner workings of the library
- **reactor-netty** is intended for netty-specific questions

Refer to each project's README for potential other sources of information.

We generally discourage opening GitHub issues for questions, in favor of the two channels above.

## 2.5.2. Our policy on deprecations

When dealing with deprecations, given a version **A.B.C**, we'll ensure that:

- deprecations introduced in version **A.B.0** will be removed **no sooner than** version **A.B+1.0**
- deprecations introduced in version **A.B.1+** will be removed **no sooner than** version **A.B+2.0**
- we'll strive to mention the following in the deprecation javadoc:

# Chapter 3. TCP Server

`Reactor Netty` provides an easy to use and configure `TcpServer`. It hides most of the `Netty` functionality that is needed to create a `TCP` server and adds `Reactive Streams` backpressure.

## 3.1. Starting and Stopping

To start a `TCP` server, you must create and configure a `TcpServer` instance. By default, the `host` is configured for any local address, and the system picks up an ephemeral port when the `bind` operation is invoked. The following example shows how to create and configure a `TcpServer` instance:

`./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/create/Application.java`

```
import reactor.netty.DisposableServer;  
import reactor.netty.tcp.TcpServer;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            TcpServer.create() ①  
                .bindNow(); ②  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Creates a `TcpServer` instance that is ready for configuring.

② Starts the server in a blocking fashion and waits for it to finish initializing.

The returned `DisposableServer` offers a simple server API, including `disposeNow()`, which shuts the server down in a blocking fashion.

### 3.1.1. Host and Port

To serve on a specific `host` and `port`, you can apply the following configuration to the `TCP` server:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/address/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .host("localhost") ①
                .port(8080)         ②
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Configures the TCP server host

② Configures the TCP server port

To serve on multiple addresses, after having configured the `TcpServer` you can bind it multiple times to obtain separate `DisposableServer`'s. All created servers will share resources such as `LoopResources` because they use the same configuration instance under the hood.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/server/address/MultiAddressApplication.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class MultiAddressApplication {

    public static void main(String[] args) {
        TcpServer tcpServer = TcpServer.create();
        DisposableServer server1 = tcpServer
            .host("localhost") ①
            .port(8080)         ②
            .bindNow();

        DisposableServer server2 = tcpServer
            .host("0.0.0.0") ③
            .port(8081)       ④
            .bindNow();

        Mono.when(server1.onDispose(), server2.onDispose())
            .block();
    }
}
```

- ① Configures the first **TCP** server host
- ② Configures the first **TCP** server port
- ③ Configures the second **TCP** server host
- ④ Configures the second **TCP** server port

## 3.2. Eager Initialization

By default, the initialization of the **TcpServer** resources happens on demand. This means that the **bind operation** absorbs the extra time needed to initialize and load:

- the event loop groups
- the native transport libraries (when native transport is used)
- the native libraries for the security (in case of **OpenSsl**)

When you need to preload these resources, you can configure the **TcpServer** as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/server/warmup/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        TcpServer tcpServer =
            TcpServer.create()
                .handle((inbound, outbound) -> inbound.receive().then());

        tcpServer.warmup() ①
            .block();

        DisposableServer server = tcpServer.bindNow();

        server.onDispose()
            .block();
    }
}
```

① Initialize and load the event loop groups, the native transport libraries and the native libraries for the security

### 3.3. Writing Data

In order to send data to a connected client, you must attach an I/O handler. The I/O handler has access to `NettyOutbound` to be able to write data. The following example shows how to attach an I/O handler:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/send/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .handle((inbound, outbound) -> outbound.sendString(Mono
.just("hello"))) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Sends `hello` string to the connected clients

## 3.4. Consuming Data

In order to receive data from a connected client, you must attach an I/O handler. The I/O handler has access to `NettyInbound` to be able to read data. The following example shows how to use it:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/read/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .handle((inbound, outbound) -> inbound.receive().then())
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Receives data from the connected clients

## 3.5. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `TcpServer`:

Callback	Description
<code>doOnBind</code>	Invoked when the server channel is about to bind.
<code>doOnBound</code>	Invoked when the server channel is bound.
<code>doOnChannelInit</code>	Invoked when initializing the channel.
<code>doOnConnection</code>	Invoked when a remote client is connected
<code>doOnUnbound</code>	Invoked when the server channel is unbound.

The following example uses the `doOnConnection` and `doOnChannelInit` callbacks:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/lifecycle/Application.java

```
import io.netty.handler.logging.LoggingHandler;
import io.netty.handler.timeout.ReadTimeoutHandler;
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;
import java.util.concurrent.TimeUnit;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .doOnConnection(conn ->
                    conn.addHandlerFirst(new ReadTimeoutHandler(10,
TimeUnit.SECONDS))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))) ②
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Netty pipeline is extended with `ReadTimeoutHandler` when a remote client is connected.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 3.6. TCP-level Configurations

This section describes three kinds of configuration that you can use at the TCP level:

- [Setting Channel Options](#)
- [Wire Logger](#)
- [Using an Event Loop Group](#)

### 3.6.1. Setting Channel Options

By default, the TCP server is configured with the following options:

*./../reactor-netty-core/src/main/java/reactor/netty/tcp/TcpServerBind.java*

```
Map<ChannelOption<?>, Boolean> childOptions = new HashMap<>(2);
childOptions.put(ChannelOption.AUTO_READ, false);
childOptions.put(ChannelOption.TCP_NODELAY, true);
this.config = new TcpServerConfig(
    Collections.singletonMap(ChannelOption.SO_REUSEADDR, true),
    childOptions,
    () -> new InetSocketAddress(DEFAULT_PORT));
}
```

If additional options are necessary or changes to the current options are needed, you can apply the following configuration:

*./../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/tcp/server/channeloptions/Application.java*

```
import io.netty.channel.ChannelOption;
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000)
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

You can find more about **Netty** channel options at the following links:

- [Common ChannelOption](#)
- [Epoll ChannelOption](#)
- [KQueue ChannelOption](#)
- [Socket Options](#)

### 3.6.2. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected.

By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.tcp.TcpServer` level to `DEBUG` and apply the following configuration:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/wiretap/Application.java
```

```
import reactor.netty.DisposableServer;  
import reactor.netty.tcp.TcpServer;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            TcpServer.create()  
                .wiretap(true) ①  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging

## Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufferFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/wiretap/custom/Application  
.java
```

```
import io.netty.handler.logging.LogLevel;  
import reactor.netty.DisposableServer;  
import reactor.netty.tcp.TcpServer;  
import reactor.netty.transport.logging.AdvancedByteBufFormat;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            TcpServer.create()  
                .wiretap("logger-name", LogLevel.DEBUG,  
AdvancedByteBufFormat.TEXTUAL) ①  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

### 3.6.3. Using an Event Loop Group

By default, the **TCP** server uses an “Event Loop Group,” where the number of the worker threads equals the number of processors available to the runtime on initialization (but with a minimum value of 4). When you need a different configuration, you can use one of the [LoopResource#create](#) methods.

The default configuration for the **Event Loop Group** is the following:

*./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java*

```
/**
 * Default worker thread count, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String IO_WORKER_COUNT = "reactor.netty.ioWorkerCount";
/**
 * Default selector thread count, fallback to -1 (no selector thread)
 */
public static final String IO_SELECT_COUNT = "reactor.netty.ioSelectCount";
/**
 * Default worker thread count for UDP, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String UDP_IO_THREAD_COUNT =
"reactor.netty.udp.ioThreadCount";
/**
 * Default quiet period that guarantees that the disposal of the underlying
LoopResources
 * will not happen, fallback to 2 seconds.
 */
public static final String SHUTDOWN_QUIET_PERIOD =
"reactor.netty.ioShutdownQuietPeriod";
/**
 * Default maximum amount of time to wait until the disposal of the underlying
LoopResources
 * regardless if a task was submitted during the quiet period, fallback to 15
seconds.
 */
public static final String SHUTDOWN_TIMEOUT = "reactor.netty.ioShutdownTimeout";
/**
 * Default value whether the native transport (epoll, kqueue) will be preferred,
 * fallback it will be preferred when available
 */
public static final String NATIVE = "reactor.netty.native";
```

If changes to the these settings are needed, you can apply the following configuration:



../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/server/eventloop/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.resources.LoopResources;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        LoopResources loop = LoopResources.create("event-loop", 1, 4, true);

        DisposableServer server =
            TcpServer.create()
                .runOn(loop)
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

## 3.7. SSL and TLS

When you need SSL or TLS, you can apply the configuration shown in the next listing. By default, if `OpenSSL` is available, `SslProvider.OPENSSL` provider is used as a provider. Otherwise `SslProvider.JDK` is used. Switching the provider can be done through `SslContextBuilder` or by setting `-Dio.netty.handler.ssl.noOpenSsl=true`.

The following example uses `SslContextBuilder`:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/security/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;
import reactor.netty.tcp.TcpSslContextSpec;

import java.io.File;

public class Application {

    public static void main(String[] args) {
        File cert = new File("certificate.crt");
        File key = new File("private.key");

        TcpSslContextSpec tcpSslContextSpec = TcpSslContextSpec.forServer(cert,
key);

        DisposableServer server =
            TcpServer.create()
                .secure(spec -> spec.sslContext(tcpSslContextSpec))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

### 3.7.1. Server Name Indication

You can configure the **TCP** server with multiple **SslContext** mapped to a specific domain. An exact domain name or a domain name containing a wildcard can be used when configuring the **SNI** mapping.

The following example uses a domain name containing a wildcard:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/sni/Application.java
```

```
import io.netty.handler.ssl.SslContext;  
import io.netty.handler.ssl.SslContextBuilder;  
import reactor.netty.DisposableServer;  
import reactor.netty.tcp.TcpServer;  
  
import java.io.File;  
  
public class Application {  
  
    public static void main(String[] args) throws Exception {  
        File defaultCert = new File("default_certificate.crt");  
        File defaultKey = new File("default_private.key");  
  
        File testDomainCert = new File("default_certificate.crt");  
        File testDomainKey = new File("default_private.key");  
  
        SslContext defaultSslContext = SslContextBuilder.forServer(defaultCert,  
defaultKey).build();  
        SslContext testDomainSslContext = SslContextBuilder.forServer  
(testDomainCert, testDomainKey).build();  
  
        DisposableServer server =  
            TcpServer.create()  
                .secure(spec -> spec.sslContext(defaultSslContext)  
                    .addSniMapping("*.test.com",  
                        testDomainSpec ->  
testDomainSpec.sslContext(testDomainSslContext)))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

## 3.8. Metrics

The TCP server supports built-in integration with **Micrometer**. It exposes all metrics with a prefix of `reactor.netty.tcp.server`.

The following table provides information for the TCP server metrics:

metric name	type	description
reactor.netty.tcp.server.connections.total	Gauge	The number of all opened connections. See <a href="#">Connections Total</a>
reactor.netty.tcp.server.data.received	DistributionSummary	Amount of the data received, in bytes. See <a href="#">Data Received</a>
reactor.netty.tcp.server.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.tcp.server.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>
reactor.netty.tcp.server.tls.handshake.time	Timer	Time spent for TLS handshake. See <a href="#">Tls Handshake Time</a>

These additional metrics are also available:

#### ByteBufAllocator metrics

metric name	type	description
reactor.netty.bytebuf.allocator.used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf.allocator.used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>
reactor.netty.bytebuf.allocator.heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf.allocator.direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>
reactor.netty.bytebuf.allocator.threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf.allocator.small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>
reactor.netty.bytebuf.allocator.normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf.allocator.chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>

metric name	type	description
reactor.netty.bytebuf.allocator. active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf.allocator. active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending .tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

`./../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/tcp/server/metrics/Application.java`

```
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .metrics(true) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Enables the built-in integration with Micrometer

When TCP server metrics are needed for an integration with a system other than [Micrometer](#) or you want to provide your own integration with [Micrometer](#), you can provide your own metrics recorder, as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/metrics/custom/Application.  
java

```
import reactor.netty.DisposableServer;
import reactor.netty.channel.ChannelMetricsRecorder;
import reactor.netty.tcp.TcpServer;

import java.net.SocketAddress;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .metrics(true, CustomChannelMetricsRecorder::new) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Enables TCP server metrics and provides `ChannelMetricsRecorder` implementation.

## 3.9. Tracing

The TCP server supports built-in integration with `Micrometer Tracing`.

The following table provides information for the TCP server spans:

contextual name	description
tls handshake	Information and time spent for TLS handshake. See <a href="#">Tls Handshake Span</a> .

The following example enables that integration. This concrete example uses `Brave` and reports the information to `Zipkin`. See the `Micrometer Tracing` documentation for `OpenTelemetry` setup.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/server/tracing/Application.java

```
import brave.Tracing;
import brave.handler.SpanHandler;
import brave.propagation.StrictCurrentTraceContext;
import brave.sampler.Sampler;
import io.micrometer.tracing.CurrentTraceContext;
import io.micrometer.tracing.Tracer;
import io.micrometer.tracing.brave.bridge.BraveBaggageManager;
import io.micrometer.tracing.brave.bridge.BraveCurrentTraceContext;
import io.micrometer.tracing.brave.bridge.BraveTracer;
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.observability.ReactorNettyTracingObservationHandler;
import reactor.netty.tcp.TcpServer;
import zipkin2.reporter.AsyncReporter;
import zipkin2.reporter.brave.ZipkinSpanHandler;
import zipkin2.reporter.urlconnection.URLConnectionSender;

import static reactor.netty.Metrics.OBSERVATION_REGISTRY;

public class Application {

    public static void main(String[] args) {
        init(); ①

        DisposableServer server =
            TcpServer.create()
                .metrics(true) ②
                .handle((inbound, outbound) -> outbound.sendString(Mono
.just("hello")))
                .bindNow();

        server.onDispose()
            .block();
    }

    /**
     * This setup is based on
     * <a
href="https://micrometer.io/docs/tracing#_micrometer_tracing_brave_setup">Micromet
er Tracing Brave Setup</a>
     */
    static void init() {
        SpanHandler spanHandler = ZipkinSpanHandler
            .create(AsyncReporter.create(URLConnectionSender.create
("http://localhost:9411/api/v2/spans")));

        StrictCurrentTraceContext braveCurrentTraceContext =
```

```

StrictCurrentTraceContext.create();

    CurrentTraceContext bridgeContext = new BraveCurrentTraceContext
(bridgeCurrentTraceContext);

    Tracing tracing =
        Tracing.newBuilder()
            .currentTraceContext(bridgeCurrentTraceContext)
            .supportsJoin(false)
            .traceId128Bit(true)
            .sampler(Sampler.ALWAYS_SAMPLE)
            .addSpanHandler(spanHandler)
            .localServiceName("reactor-netty-examples")
            .build();

    brave.Tracer braveTracer = tracing.tracer();

    Tracer tracer = new BraveTracer(braveTracer, bridgeContext, new
BraveBaggageManager());

    OBSERVATION_REGISTRY.observationConfig()
        .observationHandler(new
ReactorNettyTracingObservationHandler(tracer));
}
}

```

- ① Initializes Brave, Zipkin, and the Observation registry.
- ② Enables the built-in integration with Micrometer.

The result in **Zipkin** looks like:



## REACTOR-NETTY-EXAMPLES

tls handshake

Span ID: 6ef12ad649b0984c Parent ID: None

### Annotations



SHOW ALL ANNOTATIONS

### Tags

net.peer.name	127.0.0.1
net.peer.port	56246
reactor.netty.protocol	tcp
reactor.netty.status	SUCCESS
reactor.netty.type	server

## 3.10. Unix Domain Sockets

The **TCP** server supports Unix Domain Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/server/uds/Application.java

```
import io.netty.channel.unix.DomainSocketAddress;
import reactor.netty.DisposableServer;
import reactor.netty.tcp.TcpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            TcpServer.create()
                .bindAddress(() -> new DomainSocketAddress
("/tmp/test.sock")) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Specifies `DomainSocketAddress` that will be used

# Chapter 4. TCP Client

Reactor Netty provides the easy-to-use and easy-to-configure `TcpClient`. It hides most of the Netty functionality that is needed in order to create a `TCP` client and adds Reactive Streams backpressure.

## 4.1. Connect and Disconnect

To connect the `TCP` client to a given endpoint, you must create and configure a `TcpClient` instance. By default, the `host` is `localhost` and the `port` is `12012`. The following example shows how to create a `TcpClient`:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/create/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()      ①  
                .connectNow();    ②  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Creates a `TcpClient` instance that is ready for configuring.

② Connects the client in a blocking fashion and waits for it to finish initializing.

The returned `Connection` offers a simple connection API, including `disposeNow()`, which shuts the client down in a blocking fashion.

### 4.1.1. Host and Port

To connect to a specific `host` and `port`, you can apply the following configuration to the `TCP` client. The following example shows how to do so:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/address/Application.java

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com") ①
                .port(80)             ②
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Configures the **TCP** host

② Configures the **TCP** port

## 4.2. Eager Initialization

By default, the initialization of the **TcpClient** resources happens on demand. This means that the **connect operation** absorbs the extra time needed to initialize and load:

- the event loop group
- the host name resolver
- the native transport libraries (when native transport is used)
- the native libraries for the security (in case of **OpenSsl**)

When you need to preload these resources, you can configure the **TcpClient** as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/warmup/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        TcpClient tcpClient =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .handle((inbound, outbound) -> outbound.sendString(Mono
.just("hello"))));

        tcpClient.warmup() ①
            .block();

        Connection connection = tcpClient.connectNow(); ②

        connection.onDispose()
            .block();
    }
}
```

- ① Initialize and load the event loop group, the host name resolver, the native transport libraries and the native libraries for the security
- ② Host name resolution happens when connecting to the remote peer

## 4.3. Writing Data

To send data to a given endpoint, you must attach an I/O handler. The I/O handler has access to `NettyOutbound` to be able to write data.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/client/send/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .handle((inbound, outbound) -> outbound.sendString(Mono
.just("hello"))) ①
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Sends **hello** string to the endpoint.

When you need more control over the writing process, as an alternative for I/O handler you may use `Connection#outbound`. As opposed to I/O handler where the connection is closed when the provided `Publisher` finishes (in case of finite `Publisher`), when using `Connection#outbound`, you have to invoke explicitly `Connection#dispose` in order to close the connection.

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/send/connection/Application.  
java
```

```
import reactor.core.publisher.Mono;  
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()  
                .host("example.com")  
                .port(80)  
                .connectNow();  
  
        connection.outbound()  
            .sendString(Mono.just("hello 1")) ①  
            .then()  
            .subscribe();  
  
        connection.outbound()  
            .sendString(Mono.just("hello 2")) ②  
            .then()  
            .subscribe(null, null, connection::dispose); ③  
  
        connection.onDispose()  
            .block();  
    }  
}
```

- ① Sends **hello 1** string to the endpoint.
- ② Sends **hello 2** string to the endpoint.
- ③ Closes the connection once the message is sent to the endpoint.

## 4.4. Consuming Data

To receive data from a given endpoint, you must attach an I/O handler. The I/O handler has access to **NettyInbound** to be able to read data. The following example shows how to do so:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/client/read/Application.java

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .handle((inbound, outbound) -> inbound.receive().then())
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Receives data from a given endpoint

When you need more control over the reading process, as an alternative for I/O handler you may use `Connection#inbound`. As opposed to I/O handler where the connection is closed when the provided `Publisher` finishes (in case of finite `Publisher`), when using `Connection#inbound`, you have to invoke explicitly `Connection#dispose` in order to close the connection.



```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/read/connection/Application.  
java
```

```
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()  
                .host("example.com")  
                .port(80)  
                .connectNow();  
  
        connection.inbound()  
            .receive() ①  
            .then()  
            .subscribe();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Receives data from a given endpoint.

## 4.5. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `TcpClient`.

Callback	Description
<code>doAfterResolve</code>	Invoked after the remote address has been resolved successfully.
<code>doOnChannelInit</code>	Invoked when initializing the channel.
<code>doOnConnect</code>	Invoked when the channel is about to connect.
<code>doOnConnected</code>	Invoked after the channel has been connected.
<code>doOnDisconnected</code>	Invoked after the channel has been disconnected.
<code>doOnResolve</code>	Invoked when the remote address is about to be resolved.
<code>doOnResolveError</code>	Invoked in case the remote address hasn't been resolved successfully.

The following example uses the `doOnConnected` and `doOnChannelInit` callbacks:

`./../reactor-netty-`

`examples/src/main/java/reactor/netty/examples/documentation/tcp/client/lifecycle/Application.java`

```
import io.netty.handler.logging.LoggingHandler;
import io.netty.handler.timeout.ReadTimeoutHandler;
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;
import java.util.concurrent.TimeUnit;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .doOnConnected(conn ->
                    conn.addHandlerFirst(new ReadTimeoutHandler(10,
TimeUnit.SECONDS))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))) ②
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Netty pipeline is extended with `ReadTimeoutHandler` when the channel has been connected.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 4.6. TCP-level Configurations

This section describes three kinds of configuration that you can use at the TCP level:

- [Channel Options](#)
- [Wire Logger](#)
- [Event Loop Group](#)

### 4.6.1. Channel Options

By default, the `TCP` client is configured with the following options:

*../../reactor-netty-core/src/main/java/reactor/netty/tcp/TcpClientConnect.java*

```
this.config = new TcpClientConfig(
    provider,
    Collections.singletonMap(ChannelOption.AUTO_READ, false),
    () -> AddressUtils.createUnresolved(NetUtil.LOCALHOST.
getHostAddress(), DEFAULT_PORT));
}
```

If additional options are necessary or changes to the current options are needed, you can apply the following configuration:

*../../reactor-netty-*

*examples/src/main/java/reactor/netty/examples/documentation/tcp/client/channeloptions/Application.j*  
*ava*

```
import io.netty.channel.ChannelOption;
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000)
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

You can find more about **Netty** channel options at the following links:

- [Common ChannelOption](#)
- [Epoll ChannelOption](#)
- [KQueue ChannelOption](#)
- [Socket Options](#)

#### 4.6.2. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected.

By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.tcp.TcpClient` level to `DEBUG` and apply the following configuration:

`./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/wiretap/Application.java`

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .wiretap(true) ①
                .host("example.com")
                .port(80)
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Enables the wire logging

## Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/wiretap/custom/Application.  
java
```

```
import io.netty.handler.logging.LogLevel;  
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
import reactor.netty.transport.logging.AdvancedByteBufFormat;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()  
                .wiretap("logger-name", LogLevel.DEBUG,  
AdvancedByteBufFormat.TEXTUAL) ①  
                .host("example.com")  
                .port(80)  
                .connectNow();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

### 4.6.3. Event Loop Group

By default the [TCP](#) client uses an “Event Loop Group”, where the number of the worker threads equals the number of processors available to the runtime on initialization (but with a minimum value of 4). When you need a different configuration, you can use one of the [LoopResource#create](#) methods.

The following listing shows the default configuration for the Event Loop Group:

*./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java*

```
/**
 * Default worker thread count, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String IO_WORKER_COUNT = "reactor.netty.ioWorkerCount";
/**
 * Default selector thread count, fallback to -1 (no selector thread)
 */
public static final String IO_SELECT_COUNT = "reactor.netty.ioSelectCount";
/**
 * Default worker thread count for UDP, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String UDP_IO_THREAD_COUNT =
"reactor.netty.udp.ioThreadCount";
/**
 * Default quiet period that guarantees that the disposal of the underlying
 LoopResources
 * will not happen, fallback to 2 seconds.
 */
public static final String SHUTDOWN_QUIET_PERIOD =
"reactor.netty.ioShutdownQuietPeriod";
/**
 * Default maximum amount of time to wait until the disposal of the underlying
 LoopResources
 * regardless if a task was submitted during the quiet period, fallback to 15
 seconds.
 */
public static final String SHUTDOWN_TIMEOUT = "reactor.netty.ioShutdownTimeout";
/**
 * Default value whether the native transport (epoll, kqueue) will be preferred,
 * fallback it will be preferred when available
 */
public static final String NATIVE = "reactor.netty.native";
```

If you need changes to the these settings, you can apply the following configuration:



../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/client/eventloop/Application.java

```
import reactor.netty.Connection;
import reactor.netty.resources.LoopResources;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        LoopResources loop = LoopResources.create("event-loop", 1, 4, true);

        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .runOn(loop)
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

## 4.7. Connection Pool

By default, `TcpClient` uses a “fixed” connection pool with `500` as the maximum number of active channels and `1000` as the maximum number of further channel acquisition attempts allowed to be kept in a pending state (for the rest of the configurations check the system properties or the builder configurations below). This means that the implementation creates a new channel if someone tries to acquire a channel as long as less than `500` have been created and are managed by the pool. When the maximum number of channels in the pool is reached, up to `1000` new attempts to acquire a channel are delayed (pending) until a channel is closed (and thus a slot is free and a new connection can be opened), and further attempts are declined with an error.



Connections used by the `TcpClient` are never returned to the pool, but closed. When a connection is closed, a slot is freed in the pool and thus a new connection can be opened when needed. This behaviour is specific only for `TcpClient` and is intentional because only the user/framework knows if the actual protocol is compatible with reusing connections. (opposed to `HttpClient` where the protocol is known and Reactor Netty can return the connection to the pool when this is possible)

*./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java*

```
/**
 * Default max connections. Fallback to
 * 2 * available number of processors (but with a minimum value of 16)
 */
public static final String POOL_MAX_CONNECTIONS =
    "reactor.netty.pool.maxConnections";
/**
 * Default acquisition timeout (milliseconds) before error. If -1 will never wait
 * to
 * acquire before opening a new
 * connection in an unbounded fashion. Fallback 45 seconds
 */
public static final String POOL_ACQUIRE_TIMEOUT =
    "reactor.netty.pool.acquireTimeout";
```

When you need to change the default settings, you can configure the `ConnectionProvider` as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/pool/config/Application.java

```
import reactor.netty.Connection;
import reactor.netty.resources.ConnectionProvider;
import reactor.netty.tcp.TcpClient;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        ConnectionProvider provider =
            ConnectionProvider.builder("fixed")
                .maxConnections(50)
                .pendingAcquireTimeout(Duration.ofSeconds(60))
                .build();

        Connection connection =
            TcpClient.create(provider)
                .host("example.com")
                .port(80)
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Configures the maximum time for the pending acquire operation to 60 seconds.

The following listing shows the available configurations:

Configuration name	Description
<code>disposeInactivePoolsInBackground</code>	When this option is enabled, connection pools are regularly checked in the background, and those that are empty and been inactive for a specified time become eligible for disposal. By default, this background disposal of inactive pools is disabled.

Configuration name	Description
<code>disposeTimeout</code>	When <code>ConnectionProvider#dispose()</code> or <code>ConnectionProvider#disposeLater()</code> is called, trigger a graceful shutdown for the connection pools, with this grace period timeout. From there on, all calls for acquiring a connection will fail fast with an exception. However, for the provided <code>Duration</code> , pending acquires will get a chance to be served. Note: The rejection of new acquires and the grace timer start immediately, irrespective of subscription to the <code>Mono</code> returned by <code>ConnectionProvider#disposeLater()</code> . Subsequent calls return the same <code>Mono</code> , effectively getting notifications from the first graceful shutdown call and ignoring subsequently provided timeouts. By default, dispose timeout is not specified.
<code>maxConnections</code>	The maximum number of connections (per connection pool) before start pending. Default to $2 * \text{available number of processors}$ (but with a minimum value of 16).
<code>metrics</code>	Enables/disables built-in integration with Micrometer. <code>ConnectionProvider.MeterRegistrar</code> can be provided for integration with another metrics system. By default, metrics are not enabled.
<code>pendingAcquireMaxCount</code>	The maximum number of extra attempts at acquiring a connection to keep in a pending queue. If -1 is specified, the pending queue does not have upper limit. Default to $2 * \text{max connections}$ .
<code>pendingAcquireTimeout</code>	The maximum time before which a pending acquire must complete, or a <code>TimeoutException</code> is thrown (resolution: ms). If -1 is specified, no such timeout is applied. Default: 45 seconds.

If you need to disable the connection pool, you can apply the following configuration:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/pool/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.newConnection()  
                .host("example.com")  
                .port(80)  
                .connectNow();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

#### 4.7.1. Metrics

The pooled `ConnectionProvider` supports built-in integration with `Micrometer`. It exposes all metrics with a prefix of `reactor.netty.connection.provider`.

Pooled `ConnectionProvider` metrics

metric name	type	description
reactor.netty.connection.provider.total.connections	Gauge	The number of all connections, active or idle. See <a href="#">Total Connections</a>
reactor.netty.connection.provider.active.connections	Gauge	The number of the connections that have been successfully acquired and are in active use. See <a href="#">Active Connections</a>
reactor.netty.connection.provider.max.connections	Gauge	The maximum number of active connections that are allowed. See <a href="#">Max Connections</a>
reactor.netty.connection.provider.idle.connections	Gauge	The number of the idle connections. See <a href="#">Idle Connections</a>
reactor.netty.connection.provider.pending.connections	Gauge	The number of requests that are waiting for a connection. See <a href="#">Pending Connections</a>

metric name	type	description
reactor.netty.connection.provider.max.pending.connections	Gauge	The maximum number of requests that will be queued while waiting for a ready connection. See <a href="#">Max Pending Connections</a>

The following example enables that integration:

```
./../reactor-netty-
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/pool/metrics/Application.java
```

```
import reactor.netty.Connection;
import reactor.netty.resources.ConnectionProvider;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        ConnectionProvider provider =
            ConnectionProvider.builder("fixed")
                .maxConnections(50)
                .metrics(true) ①
                .build();

        Connection connection =
            TcpClient.create(provider)
                .host("example.com")
                .port(80)
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Enables the built-in integration with Micrometer

## 4.8. SSL and TLS

When you need SSL or TLS, you can apply the following configuration. By default, if **OpenSSL** is available, the `SslProvider.OPENSSL` provider is used as a provider. Otherwise, the provider is `SslProvider.JDK`. You can switch the provider by using `SslContextBuilder` or by setting `-Dio.netty.handler.ssl.noOpenSsl=true`.

The following example uses `SslContextBuilder`:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/client/security/Application.java

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;
import reactor.netty.tcp.TcpSslContextSpec;

public class Application {

    public static void main(String[] args) {
        TcpSslContextSpec tcpSslContextSpec = TcpSslContextSpec.forClient();

        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(443)
                .secure(spec -> spec.sslContext(tcpSslContextSpec))
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

### 4.8.1. Server Name Indication

By default, the **TCP** client sends the remote host name as **SNI** server name. When you need to change this default setting, you can configure the **TCP** client as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/sni/Application.java
```

```
import io.netty.handler.ssl.SslContext;  
import io.netty.handler.ssl.SslContextBuilder;  
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
import javax.net.ssl.SNIHostName;  
  
public class Application {  
  
    public static void main(String[] args) throws Exception {  
        SslContext sslContext = SslContextBuilder.forClient().build();  
  
        Connection connection =  
            TcpClient.create()  
                .host("127.0.0.1")  
                .port(8080)  
                .secure(spec -> spec.sslContext(sslContext)  
                    .serverNames(new SNIHostName  
("test.com")))  
                .connectNow();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

## 4.9. Proxy Support

Reactor Netty supports the proxy functionality provided by Netty and provides a way to specify **non proxy hosts** through the **ProxyProvider** builder.

Netty's HTTP proxy support always uses **CONNECT** method in order to establish a tunnel to the specified proxy regardless of the scheme that is used **http** or **https**. (More information: [Netty enforce HTTP proxy to support HTTP CONNECT method](#)). Some proxies might not support **CONNECT** method when the scheme is **http** or might need to be configured in order to support this way of communication. Sometimes this might be the reason for not being able to connect to the proxy. Consider checking the proxy documentation whether it supports or needs an additional configuration in order to support **CONNECT** method.

The following example uses **ProxyProvider**:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/proxy/Application.java

```
import reactor.netty.Connection;
import reactor.netty.transport.ProxyProvider;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .proxy(spec -> spec.type(ProxyProvider.Proxy.SOCKS4)
                    .host("proxy")
                    .port(8080)
                    .nonProxyHosts("localhost")
                    .connectTimeoutMillis(20_000)) ①
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Configures the connection establishment timeout to 20 seconds.

## 4.10. Metrics

The TCP client supports built-in integration with [Micrometer](#). It exposes all metrics with a prefix of `reactor.netty.tcp.client`.

The following table provides information for the TCP client metrics:

metric name	type	description
reactor.netty.tcp.client.data.received	DistributionSummary	Amount of the data received, in bytes. See <a href="#">Data Received</a>
reactor.netty.tcp.client.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.tcp.client.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>
reactor.netty.tcp.client.tls.handshake.time	Timer	Time spent for TLS handshake. See <a href="#">Tls Handshake Time</a>

metric name	type	description
reactor.netty.tcp.client.connect.time	Timer	Time spent for connecting to the remote address. See <a href="#">Connect Time</a>
reactor.netty.tcp.client.address.resolver	Timer	Time spent for resolving the address. See <a href="#">Hostname Resolution Time</a>

These additional metrics are also available:

Pooled **ConnectionProvider** metrics

metric name	type	description
reactor.netty.connection.provider.total.connections	Gauge	The number of all connections, active or idle. See <a href="#">Total Connections</a>
reactor.netty.connection.provider.active.connections	Gauge	The number of the connections that have been successfully acquired and are in active use. See <a href="#">Active Connections</a>
reactor.netty.connection.provider.max.connections	Gauge	The maximum number of active connections that are allowed. See <a href="#">Max Connections</a>
reactor.netty.connection.provider.idle.connections	Gauge	The number of the idle connections. See <a href="#">Idle Connections</a>
reactor.netty.connection.provider.pending.connections	Gauge	The number of requests that are waiting for a connection. See <a href="#">Pending Connections</a>
reactor.netty.connection.provider.max.pending.connections	Gauge	The maximum number of requests that will be queued while waiting for a ready connection. See <a href="#">Max Pending Connections</a>

**ByteBufferAllocator** metrics

metric name	type	description
reactor.netty.bytebuf.allocator.used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf.allocator.used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>

metric name	type	description
reactor.netty.bytebuf allocator.heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf allocator.direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>
reactor.netty.bytebuf allocator.threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf allocator.small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>
reactor.netty.bytebuf allocator.normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf allocator.chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>
reactor.netty.bytebuf allocator.active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf allocator.active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending.tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/metrics/Application.java

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .metrics(true) ①
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Enables the built-in integration with Micrometer

When TCP client metrics are needed for an integration with a system other than **Micrometer** or you want to provide your own integration with **Micrometer**, you can provide your own metrics recorder, as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/metrics/custom/Application.j  
ava
```

```
import reactor.netty.Connection;  
import reactor.netty.channel.ChannelMetricsRecorder;  
import reactor.netty.tcp.TcpClient;  
  
import java.net.SocketAddress;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()  
                .host("example.com")  
                .port(80)  
                .metrics(true, CustomChannelMetricsRecorder::new) ①  
                .connectNow();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Enables TCP client metrics and provides `ChannelMetricsRecorder` implementation.

## 4.11. Tracing

The TCP client supports built-in integration with `Micrometer Tracing`.

The following table provides information for the TCP client spans:

contextual name	description
hostname resolution	Information and time spent for resolving the address. See <a href="#">Hostname Resolution Span</a> .
connect	Information and time spent for connecting to the remote address. See <a href="#">Connect Span</a> .
tls handshake	Information and time spent for TLS handshake. See <a href="#">Tls Handshake Span</a> .

The following example enables that integration. This concrete example uses `Brave` and reports the information to `Zipkin`. See the `Micrometer Tracing` documentation for `OpenTelemetry` setup.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/tcp/client/tracing/Application.java

```
import brave.Tracing;
import brave.handler.SpanHandler;
import brave.propagation.StrictCurrentTraceContext;
import brave.sampler.Sampler;
import io.micrometer.tracing.CurrentTraceContext;
import io.micrometer.tracing.Tracer;
import io.micrometer.tracing.brave.bridge.BraveBaggageManager;
import io.micrometer.tracing.brave.bridge.BraveCurrentTraceContext;
import io.micrometer.tracing.brave.bridge.BraveTracer;
import reactor.netty.Connection;
import reactor.netty.observability.ReactorNettyTracingObservationHandler;
import reactor.netty.tcp.TcpClient;
import zipkin2.reporter.AsyncReporter;
import zipkin2.reporter.brave.ZipkinSpanHandler;
import zipkin2.reporter.urlconnection.URLConnectionSender;

import static reactor.netty.Metrics.OBSERVATION_REGISTRY;

public class Application {

    public static void main(String[] args) {
        init(); ①

        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .metrics(true) ②
                .connectNow();

        connection.onDispose()
            .block();
    }

    /**
     * This setup is based on
     * <a
href="https://micrometer.io/docs/tracing#_micrometer_tracing_brave_setup">Micromet
er Tracing Brave Setup</a>
     */
    static void init() {
        SpanHandler spanHandler = ZipkinSpanHandler
            .create(AsyncReporter.create(URLConnectionSender.create
("http://localhost:9411/api/v2/spans"))));

        StrictCurrentTraceContext braveCurrentTraceContext =
            StrictCurrentTraceContext.create();
    }
}
```

```

    CurrentTraceContext bridgeContext = new BraveCurrentTraceContext
(braveCurrentTraceContext);

    Tracing tracing =
        Tracing.newBuilder()
            .currentTraceContext(braveCurrentTraceContext)
            .supportsJoin(false)
            .traceId128Bit(true)
            .sampler(Sampler.ALWAYS_SAMPLE)
            .addSpanHandler(spanHandler)
            .localServiceName("reactor-netty-examples")
            .build();

    brave.Tracer braveTracer = tracing.tracer();

    Tracer tracer = new BraveTracer(braveTracer, bridgeContext, new
BraveBaggageManager());

    OBSERVATION_REGISTRY.observationConfig()
        .observationHandler(new
ReactorNettyTracingObservationHandler(tracer));
}
}

```

- ① Initializes Brave, Zipkin, and the Observation registry.
- ② Enables the built-in integration with Micrometer.

The result in **Zipkin** looks like:

REACTOR-NETTY-EXAMPLES  
connect

Span ID: adf57b92fc14f0e2 Parent ID: None

### Annotations

SHOW ALL ANNOTATIONS

### Tags

net.peer.name	example.com
net.peer.port	80
reactor.netty.protocol	tcp
reactor.netty.status	SUCCESS
reactor.netty.type	client

## 4.12. Unix Domain Sockets

The **TcpClient** supports Unix Domain Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/uds/Application.java
```

```
import io.netty.channel.unix.DomainSocketAddress;  
import reactor.netty.Connection;  
import reactor.netty.tcp.TcpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            TcpClient.create()  
                .remoteAddress(() -> new DomainSocketAddress  
("/tmp/test.sock")) ①  
                .connectNow();  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Specifies **DomainSocketAddress** that will be used

## 4.13. Host Name Resolution

By default, the **TcpClient** uses Netty's domain name lookup mechanism that resolves a domain name asynchronously. This is as an alternative of the JVM's built-in blocking resolver.

When you need to change the default settings, you can configure the **TcpClient** as follows:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/resolver/Application.java

```
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .resolver(spec -> spec.queryTimeout(Duration.ofMillis(
500))) ①
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① The timeout of each DNS query performed by this resolver will be 500ms.

The following listing shows the available configurations:

Configuration name	Description
<code>cacheMaxTimeToLive</code>	The max time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is greater than this max time to live, this resolver ignores the time to live from the DNS server and uses use this max time to live. Default to <code>Integer.MAX_VALUE</code> .
<code>cacheMinTimeToLive</code>	The min time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is less than this min time to live, this resolver ignores the time to live from the DNS server and uses this min time to live. Default: 0.
<code>cacheNegativeTimeToLive</code>	The time to live of the cache for the failed DNS queries (resolution: seconds). Default: 0.

Configuration name	Description
<code>completeOncePreferredResolved</code>	When this setting is enabled, the resolver notifies as soon as all queries for the preferred address type are complete. When this setting is disabled, the resolver notifies when all possible address types are complete. This configuration is applicable for <code>DnsNameResolver#resolveAll(String)</code> . By default, this setting is enabled.
<code>disableOptionalRecord</code>	Disables the automatic inclusion of an optional record that tries to give a hint to the remote DNS server about how much data the resolver can read per response. By default, this setting is enabled.
<code>disableRecursionDesired</code>	Specifies whether this resolver has to send a DNS query with the recursion desired (RD) flag set. By default, this setting is enabled.
<code>hostsFileEntriesResolver</code>	Sets a custom <code>HostsFileEntriesResolver</code> to be used for hosts file entries. Default: <code>DefaultHostsFileEntriesResolver</code> .
<code>maxPayloadSize</code>	Sets the capacity of the datagram packet buffer (in bytes). Default: 4096.
<code>maxQueriesPerResolve</code>	Sets the maximum allowed number of DNS queries to send when resolving a host name. Default: 16.
<code>ndots</code>	Sets the number of dots that must appear in a name before an initial absolute query is made. Default: -1 (to determine the value from the OS on Unix or use a value of 1 otherwise).
<code>queryTimeout</code>	Sets the timeout of each DNS query performed by this resolver (resolution: milliseconds). Default: 5000.
<code>resolvedAddressTypes</code>	The list of the protocol families of the resolved address.
<code>bindAddressSupplier</code>	The supplier of the local address to bind to.
<code>roundRobinSelection</code>	Enables an <code>AddressResolverGroup</code> of <code>DnsNameResolver</code> that supports random selection of destination addresses if multiple are provided by the nameserver. See <code>RoundRobinDnsAddressResolverGroup</code> . Default: <code>DnsAddressResolverGroup</code>

Configuration name	Description
<code>runOn</code>	Performs the communication with the DNS servers on the given <code>LoopResources</code> . By default, the <code>LoopResources</code> specified on the client level are used.
<code>searchDomains</code>	The list of search domains of the resolver. By default, the effective search domain list is populated by using the system DNS search domains.
<code>trace</code>	A specific logger and log level to be used by this resolver when generating detailed trace information in case of resolution failure.

Sometimes, you may want to switch to the JVM built-in resolver. To do so, you can configure the `TcpClient` as follows:

```
./../reactor-netty-
examples/src/main/java/reactor/netty/examples/documentation/tcp/client/resolver/custom/Application.
java
```

```
import io.netty.resolver.DefaultAddressResolverGroup;
import reactor.netty.Connection;
import reactor.netty.tcp.TcpClient;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            TcpClient.create()
                .host("example.com")
                .port(80)
                .resolver(DefaultAddressResolverGroup.INSTANCE) ①
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Sets the JVM built-in resolver.

# Chapter 5. HTTP Server

**Reactor Netty** provides the easy-to-use and easy-to-configure **HttpServer** class. It hides most of the **Netty** functionality that is needed in order to create a **HTTP** server and adds **Reactive Streams** backpressure.

## 5.1. Starting and Stopping

To start an HTTP server, you must create and configure a **HttpServer** instance. By default, the **host** is configured for any local address, and the system picks up an ephemeral port when the **bind** operation is invoked. The following example shows how to create an **HttpServer** instance:

*./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/create/Application.java*

```
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create() ①
                .bindNow(); ②

        server.onDispose()
            .block();
    }
}
```

① Creates an **HttpServer** instance ready for configuring.

② Starts the server in a blocking fashion and waits for it to finish initializing.

The returned **DisposableServer** offers a simple server API, including **disposeNow()**, which shuts the server down in a blocking fashion.

### 5.1.1. Host and Port

To serve on a specific **host** and **port**, you can apply the following configuration to the **HTTP** server:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/address/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .host("localhost") ①
                .port(8080)         ②
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Configures the HTTP server host

② Configures the HTTP server port

To serve on multiple addresses, after having configured the `HttpServer` you can bind it multiple times to obtain separate `DisposableServer`'s. All created servers will share resources such as `LoopResources` because they use the same configuration instance under the hood.

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/address/MultiAddressApplication.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class MultiAddressApplication {
    public static void main(String[] args) {
        HttpServer httpServer = HttpServer.create();
        DisposableServer server1 = httpServer
            .host("localhost") ①
            .port(8080)         ②
            .bindNow();

        DisposableServer server2 = httpServer
            .host("0.0.0.0") ③
            .port(8081)       ④
            .bindNow();

        Mono.when(server1.onDispose(), server2.onDispose())
            .block();
    }
}
```

- ① Configures the first HTTP server host
- ② Configures the first HTTP server port
- ③ Configures the second HTTP server host
- ④ Configures the second HTTP server port

## 5.2. Eager Initialization

By default, the initialization of the `HttpServer` resources happens on demand. This means that the `bind operation` absorbs the extra time needed to initialize and load:

- the event loop groups
- the native transport libraries (when native transport is used)
- the native libraries for the security (in case of `OpenSsl`)

When you need to preload these resources, you can configure the `HttpServer` as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/warmup/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        HttpServer httpServer =
            HttpServer.create()
                .handle((request, response) -> request.receive().
then());

        httpServer.warmup() ①
            .block();

        DisposableServer server = httpServer.bindNow();

        server.onDispose()
            .block();
    }
}
```

① Initialize and load the event loop groups, the native transport libraries and the native libraries for the security

## 5.3. Routing HTTP

Defining routes for the **HTTP** server requires configuring the provided **HttpServerRoutes** builder. The following example shows how to do so:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/routing/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .route(routes ->
                    routes.get("/hello", ①
                        (request, response) -> response.
sendString(Mono.just("Hello World!")))
                    .post("/echo", ②
                        (request, response) -> response.send
(request.receive().retain()))
                    .get("/path/{param}", ③
                        (request, response) -> response.
sendString(Mono.just(request.param("param"))))
                    .ws("/ws", ④
                        (wsInbound, wsOutbound) -> wsOutbound.
send(wsInbound.receive().retain()))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

- ① Serves a **GET** request to **/hello** and returns **Hello World!**
- ② Serves a **POST** request to **/echo** and returns the received request body as a response.
- ③ Serves a **GET** request to **/path/{param}** and returns the value of the path parameter.
- ④ Serves websocket to **/ws** and returns the received incoming data as outgoing data.



The server routes are unique and only the first matching in order of declaration is invoked.

### 5.3.1. SSE

The following code shows how you can configure the **HTTP** server to serve **Server-Sent Events**:



../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/sse/Application.java

```
import com.fasterxml.jackson.databind.ObjectMapper;
import io.netty.buffer.ByteBuf;
import io.netty.buffer.ByteBufAllocator;
import org.reactivestreams.Publisher;
import reactor.core.publisher.Flux;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;
import reactor.netty.http.server.HttpServerRequest;
import reactor.netty.http.server.HttpServerResponse;

import java.io.ByteArrayOutputStream;
import java.nio.charset.Charset;
import java.time.Duration;
import java.util.function.BiFunction;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .route(routes -> routes.get("/sse", serveSse()))
                .bindNow();

        server.onDispose()
            .block();
    }

    /**
     * Prepares SSE response
     * The "Content-Type" is "text/event-stream"
     * The flushing strategy is "flush after every element" emitted by the
     provided Publisher
     */
    private static BiFunction<HttpServerRequest, HttpServerResponse, Publisher
<Void>> serveSse() {
        Flux<Long> flux = Flux.interval(Duration.ofSeconds(10));
        return (request, response) ->
            response.sse()
                .send(flux.map(Application::toByteBuf), b -> true);
    }

    /**
     * Transforms the Object to ByteBuf following the expected SSE format.
     */
    private static ByteBuf toByteBuf(Object any) {
        ByteArrayOutputStream out = new ByteArrayOutputStream();
        try {
```

```

        out.write("data: ".getBytes(Charset.defaultCharset()));
        MAPPER.writeValue(out, any);
        out.write("\n\n".getBytes(Charset.defaultCharset()));
    }
    catch (Exception e) {
        throw new RuntimeException(e);
    }
    return ByteBufAllocator.DEFAULT
        .buffer()
        .writeBytes(out.toByteArray());
}

private static final ObjectMapper MAPPER = new ObjectMapper();
}

```

### 5.3.2. Static Resources

The following code shows how you can configure the **HTTP** server to serve static resources:

*../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/staticresources/Application.  
java*

```

import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

import java.net.URISyntaxException;
import java.nio.file.Path;
import java.nio.file.Paths;

public class Application {

    public static void main(String[] args) throws URISyntaxException {
        Path file = Paths.get(Application.class.getResource("/logback.xml").
toURI());
        DisposableServer server =
            HttpServer.create()
                .route(routes -> routes.file("/index.html", file))
                .bindNow();

        server.onDispose()
            .block();
    }
}

```

## 5.4. Writing Data

To send data to a connected client, you must attach an I/O handler by using either `handle(...)` or `route(...)`. The I/O handler has access to `HttpServerResponse`, to be able to write data. The following example uses the `handle(...)` method:

`../../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/http/server/send/Application.java`

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .handle((request, response) -> response.sendString(Mono
                    .just("hello"))) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Sends `hello` string to the connected clients

### 5.4.1. Adding Headers and Other Metadata

When you send data to the connected clients, you may need to send additional headers, cookies, status code, and other metadata. You can provide this additional metadata by using `HttpServerResponse`. The following example shows how to do so:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/send/headers/Application.j  
ava
```

```
import io.netty.handler.codec.http.HttpHeaderNames;  
import io.netty.handler.codec.http.HttpResponseStatus;  
import reactor.core.publisher.Mono;  
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .route(routes ->  
                    routes.get("/hello",  
                        (request, response) ->  
                            response.status(HttpResponseStatus.OK)  
                                .header(HttpHeaderNames  
.  
CONTENT_LENGTH, "12")  
                                .sendString(Mono.just("Hello  
World!")))))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

### 5.4.2. Compression

You can configure the **HTTP** server to send a compressed response, depending on the request header **Accept-Encoding**.

**Reactor Netty** provides three different strategies for compressing the outgoing data:

- **compress(boolean)**: Depending on the boolean that is provided, the compression is enabled (**true**) or disabled (**false**).
- **compress(int)**: The compression is performed once the response size exceeds the given value (in bytes).
- **compress(BiPredicate<HttpServerRequest, HttpServerResponse>)**: The compression is performed if the predicate returns **true**.

The following example uses the **compress** method (set to **true**) to enable compression:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/compression/Application.j  
ava
```

```
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
  
import java.net.URISyntaxException;  
import java.nio.file.Path;  
import java.nio.file.Paths;  
  
public class Application {  
  
    public static void main(String[] args) throws URISyntaxException {  
        Path file = Paths.get(Application.class.getResource("/logback.xml").  
toURI());  
        DisposableServer server =  
            HttpServer.create()  
                .compress(true)  
                .route(routes -> routes.file("/index.html", file))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

## 5.5. Consuming Data

To receive data from a connected client, you must attach an I/O handler by using either `handle(...)` or `route(...)`. The I/O handler has access to `HttpRequest`, to be able to read data.

The following example uses the `handle(...)` method:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/read/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .handle((request, response) -> request.receive().then())
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Receives data from the connected clients

### 5.5.1. Reading Headers, URI Params, and other Metadata

When you receive data from the connected clients, you might need to check request headers, parameters, and other metadata. You can obtain this additional metadata by using `HttpRequest`. The following example shows how to do so:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/read/headers/Application.j  
ava
```

```
import reactor.core.publisher.Mono;  
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .route(routes ->  
                    routes.get("/{param}",  
                        (request, response) -> {  
                            if (request.requestHeaders().contains("Some-  
Header")) {  
                                return response.sendString(Mono.just  
(request.param("param")));  
                            }  
                            return response.sendNotFound();  
                        }  
                    )))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

### 5.5.2. Reading Post Form or Multipart Data

When you receive data from the connected clients, you might want to access **POST form** (**application/x-www-form-urlencoded**) or **multipart** (**multipart/form-data**) data. You can obtain this data by using **HttpRequest**.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/multipart/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .route(routes ->
                    routes.post("/multipart", (request, response) ->
                        response.sendString(
                            request.receiveForm() ①
                                .flatMap(data -> Mono.just('[' +
                                    data.getName() + '']'))))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Receives POST form/multipart data.

When you need to change the default settings, you can configure the `HttpServer` or you can provide a configuration per request:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/multipart/custom/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .httpFormDecoder(builder -> builder.maxInMemorySize(0))
                .route(routes ->
                    routes.post("/multipart", (request, response) ->
                        response.sendString(
                            request.receiveForm(builder -> builder
                                .flatMap(data -> Mono.just('[' +
                                    data.getName() + '']'))))
                                .bindNow());

        server.onDispose()
            .block();
    }
}
```

- ① Configuration on the `HttpServer` that specifies that the data is stored on disk only.
- ② Configuration per request that specifies that if the data size exceed the specified size, the data is stored on the disk.

The following listing shows the available configurations:

Configuration name	Description
<code>baseDirectory</code>	Configures the directory where to store the data on the disk. Default to generated temp directory.
<code>charset</code>	Configures the <code>Charset</code> for the data. Default to <code>StandardCharsets.UTF_8</code> .
<code>maxInMemorySize</code>	Configures the maximum in-memory size per data i.e. the data is written on disk if the size is greater than <code>maxInMemorySize</code> , else it is in memory. If set to <code>-1</code> the entire contents is stored in memory. If set to <code>0</code> the entire contents is stored on disk. Default to <code>16kb</code> .

Configuration name	Description
<code>maxSize</code>	Configures the maximum size per data. When the limit is reached, an exception is raised. If set to <code>-1</code> this means no limitation. Default to <code>-1</code> - unlimited.
<code>scheduler</code>	Configures the scheduler to be used for offloading disk operations in the decoding phase. Default to <code>Schedulers#boundedElastic()</code>
<code>streaming</code>	When set to <code>true</code> , the data is streamed directly from the parsed input buffer stream, which means it is not stored either in memory or file. When <code>false</code> , parts are backed by in-memory and/or file storage. Default to <code>false</code> . <b>NOTE</b> that with streaming enabled, the provided data might not be in a complete state i.e. <code>HttpData#isCompleted()</code> has to be checked. Also note that enabling this property effectively ignores <code>maxInMemorySize</code> , <code>baseDirectory</code> , and <code>scheduler</code> .

### Obtaining the Remote (Client) Address

In addition to the metadata that you can obtain from the request, you can also receive the `host` (server) address, the `remote` (client) address and the `scheme`. Depending on the chosen factory method, you can retrieve the information directly from the channel or by using the `Forwarded` or `X-Forwarded-*` HTTP request headers. The following example shows how to do so:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/clientaddress/Application.j  
ava

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .forwarded(true) ①
                .route(routes ->
                    routes.get("/clientip",
                        (request, response) ->
                            response.sendString(Mono.just(request
.remoteAddress() ②
.getHostString()))))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

- ① Specifies that the information about the connection is to be obtained from the **Forwarded** and **X-Forwarded-\*** HTTP request headers, if possible.
- ② Returns the address of the remote (client) peer.

It is also possible to customize the behavior of the **Forwarded** or **X-Forwarded-\*** header handler. The following example shows how to do so:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/clientaddress/CustomForwardedHeaderHandlerApplication.java

```
import java.net.InetSocketAddress;

import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;
import reactor.netty.transport.AddressUtils;

public class CustomForwardedHeaderHandlerApplication {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .forwarded((connectionInfo, request) -> { ①
                    String hostHeader = request.headers().get("X-Forwarded-Host");

                    if (hostHeader != null) {
                        String[] hosts = hostHeader.split(",", 2);
                        InetSocketAddress hostAddress = AddressUtils
                            .createUnresolved(
                                hosts[hosts.length - 1].trim(),
                                connectionInfo.getHostAddress().getPort());
                        connectionInfo = connectionInfo.withHostAddress(
                            hostAddress);
                    }
                    return connectionInfo;
                })
                .route(routes ->
                    routes.get("/clientip",
                        (request, response) ->
                            response.sendString(Mono.just(request
                                .remoteAddress() ②
                                    .getHostString()))))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Add a custom header handler.

② Returns the address of the remote (client) peer.

### 5.5.3. HTTP Request Decoder

By default, **Netty** configures some restrictions for the incoming requests, such as:

- The maximum length of the initial line.
- The maximum length of all headers.
- The maximum length of the content or each chunk.

For more information, see [HttpRequestDecoder](#) and [HttpServerUpgradeHandler](#)

By default, the **HTTP** server is configured with the following settings:

*./../reactor-netty-http/src/main/java/reactor/netty/http/HttpDecoderSpec.java*

```
public static final int DEFAULT_MAX_INITIAL_LINE_LENGTH           = 4096;
public static final int DEFAULT_MAX_HEADER_SIZE                  = 8192;
/**
 * @deprecated as of 1.1.0. This will be removed in 2.0.0 as Netty 5 does not
 * support this configuration.
 */
@Deprecated
public static final int DEFAULT_MAX_CHUNK_SIZE                   = 8192;
public static final boolean DEFAULT_VALIDATE_HEADERS              = true;
public static final int DEFAULT_INITIAL_BUFFER_SIZE              = 128;
public static final boolean DEFAULT_ALLOW_DUPLICATE_CONTENT_LENGTHS = false;
```

*./../reactor-netty-http/src/main/java/reactor/netty/http/server/HttpRequestDecoderSpec.java*

```
/**
 * The maximum length of the content of the HTTP/2.0 clear-text upgrade request.
 * By default, the server will reject an upgrade request with non-empty content,
 * because the upgrade request is most likely a GET request.
 */
public static final int DEFAULT_H2C_MAX_CONTENT_LENGTH = 0;
```

When you need to change these default settings, you can configure the **HTTP** server as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/requestdecoder/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .httpRequestDecoder(spec -> spec.maxHeaderSize(16384))
                .handle((request, response) -> response.sendString(Mono
                    .just("hello")))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① The maximum length of all headers will be 16384. When this value is exceeded, a `TooLongFrameException` is raised.

## 5.6. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `HttpServer`:

Callback	Description
<code>doOnBind</code>	Invoked when the server channel is about to bind.
<code>doOnBound</code>	Invoked when the server channel is bound.
<code>doOnChannelInit</code>	Invoked when initializing the channel.
<code>doOnConnection</code>	Invoked when a remote client is connected
<code>doOnUnbound</code>	Invoked when the server channel is unbound.

The following example uses the `doOnConnection` and `doOnChannelInit` callbacks:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/lifecycle/Application.java

```
import io.netty.handler.logging.LoggingHandler;
import io.netty.handler.timeout.ReadTimeoutHandler;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;
import java.util.concurrent.TimeUnit;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .doOnConnection(conn ->
                    conn.addHandlerFirst(new ReadTimeoutHandler(10,
TimeUnit.SECONDS))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))) ②
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Netty pipeline is extended with `ReadTimeoutHandler` when a remote client is connected.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 5.7. TCP-level Configuration

When you need to change configuration on the TCP level, you can use the following snippet to extend the default TCP server configuration:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/channeloptions/Application.java

```
import io.netty.channel.ChannelOption;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000)
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

See [TCP Server](#) for more detail about TCP-level configuration.

### 5.7.1. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected. By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.http.server.HttpServer` level to `DEBUG` and apply the following configuration:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/wiretap/Application.java

```
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
  
public class Application {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .wiretap(true) ①  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging

## Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufferFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

*./../reactor-netty-http/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java*

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

*./../reactor-netty-http/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java*

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/wiretap/custom/Application.java

```
import io.netty.handler.logging.LogLevel;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;
import reactor.netty.transport.logging.AdvancedByteBufFormat;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .wiretap("logger-name", LogLevel.DEBUG,
AdvancedByteBufFormat.TEXTUAL) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

## 5.8. SSL and TLS

When you need SSL or TLS, you can apply the configuration shown in the next example. By default, if `OpenSSL` is available, `SslProvider.OPENSSL` provider is used as a provider. Otherwise `SslProvider.JDK` is used. You can switch the provider by using `SslContextBuilder` or by setting `-Dio.netty.handler.ssl.noOpenSsl=true`.

The following example uses `SslContextBuilder`:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/security/Application.java

```
import reactor.netty.DisposableServer;
import reactor.netty.http.Http11SslContextSpec;
import reactor.netty.http.server.HttpServer;
import java.io.File;

public class Application {

    public static void main(String[] args) {
        File cert = new File("certificate.crt");
        File key = new File("private.key");

        Http11SslContextSpec http11SslContextSpec = Http11SslContextSpec.
forServer(cert, key);

        DisposableServer server =
            HttpServer.create()
                .secure(spec -> spec.sslContext(http11SslContextSpec))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

### 5.8.1. Server Name Indication

You can configure the **HTTP** server with multiple **SslContext** mapped to a specific domain. An exact domain name or a domain name containing a wildcard can be used when configuring the **SNI** mapping.

The following example uses a domain name containing a wildcard:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/sni/Application.java

```
import io.netty.handler.ssl.SslContext;
import io.netty.handler.ssl.SslContextBuilder;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

import java.io.File;

public class Application {

    public static void main(String[] args) throws Exception {
        File defaultCert = new File("default_certificate.crt");
        File defaultKey = new File("default_private.key");

        File testDomainCert = new File("default_certificate.crt");
        File testDomainKey = new File("default_private.key");

        SslContext defaultSslContext = SslContextBuilder.forServer(defaultCert,
defaultKey).build();
        SslContext testDomainSslContext = SslContextBuilder.forServer
(testDomainCert, testDomainKey).build();

        DisposableServer server =
            HttpServer.create()
                .secure(spec -> spec.sslContext(defaultSslContext)
                    .addSniMapping("*.test.com",
                        testDomainSpec ->
testDomainSpec.sslContext(testDomainSslContext)))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

## 5.9. HTTP Access Log

You can enable the **HTTP** access log either programmatically or by configuration. By default, it is disabled.

You can use `-Dreactor.netty.http.server.accessLogEnabled=true` to enable the **HTTP** access log by configuration.

You can use the following configuration (for Logback or similar logging frameworks) to have a separate **HTTP** access log file:

```

<appender name="accessLog" class="ch.qos.logback.core.FileAppender">
  <file>access_log.log</file>
  <encoder>
    <pattern>%msg%n</pattern>
  </encoder>
</appender>
<appender name="async" class="ch.qos.logback.classic.AsyncAppender">
  <appender-ref ref="accessLog" />
</appender>

<logger name="reactor.netty.http.server.AccessLog" level="INFO" additivity=
"false">
  <appender-ref ref="async"/>
</logger>

```

The following example enables it programmatically:

```

./../reactor-netty-
examples/src/main/java/reactor/netty/examples/documentation/http/server/accessLog/Application.java

```

```

import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .accessLog(true)
                .bindNow();

        server.onDispose()
            .block();
    }
}

```

Calling this method takes precedence over the system property configuration.

By default, the logging format is [Common Log Format](#), but you can specify a custom one as a parameter, as in the following example:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/accessLog/CustomLogAcce  
ssFormatApplication.java
```

```
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
import reactor.netty.http.server.logging.AccessLog;  
  
public class CustomLogAccessFormatApplication {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .accessLog(true, x -> AccessLog.create("method={},  
uri={}", x.method(), x.uri()))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

You can also filter HTTP access logs by using the `AccessLogFactory#createFilter` method, as in the following example:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/accessLog/FilterLogAccess  
Application.java
```

```
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
import reactor.netty.http.server.logging.AccessLogFactory;  
  
public class FilterLogAccessApplication {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .accessLog(true, AccessLogFactory.createFilter(p ->  
!String.valueOf(p.uri()).startsWith("/health/")))  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```



Note that this method can take a custom format parameter too, as in this example:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/accessLog/CustomFormat  
AndFilterAccessLogApplication.java.java
```

```
import reactor.netty.DisposableServer;  
import reactor.netty.http.server.HttpServer;  
import reactor.netty.http.server.logging.AccessLog;  
import reactor.netty.http.server.logging.AccessLogFactory;  
  
public class CustomFormatAndFilterAccessLogApplication {  
  
    public static void main(String[] args) {  
        DisposableServer server =  
            HttpServer.create()  
                .accessLog(true, AccessLogFactory.createFilter(p ->  
!String.valueOf(p.uri()).startsWith("/health/"), ①  
                x -> AccessLog.create("method={}, uri={}", x  
.method(), x.uri())) ②  
                .bindNow();  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Specifies the filter predicate to use

② Specifies the custom format to apply

## 5.10. HTTP/2

By default, the **HTTP** server supports **HTTP/1.1**. If you need **HTTP/2**, you can get it through configuration. In addition to the protocol configuration, if you need **H2** but not **H2C** (**clear text**), you must also configure SSL.



As Application-Layer Protocol Negotiation (ALPN) is not supported “out-of-the-box” by JDK8 (although some vendors backported ALPN to JDK8), you need an additional dependency to a native library that supports it—for example, **netty-tcnative-boringssl-static**.

The following listing presents a simple **H2** example:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/http2/H2Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.Http2SslContextSpec;
import reactor.netty.http.HttpProtocol;
import reactor.netty.http.server.HttpServer;
import java.io.File;

public class H2Application {

    public static void main(String[] args) {
        File cert = new File("certificate.crt");
        File key = new File("private.key");

        Http2SslContextSpec http2SslContextSpec = Http2SslContextSpec.forServer
(cert, key);

        DisposableServer server =
            HttpServer.create()
                .port(8080)
                .protocol(HttpProtocol.H2) ①
                .secure(spec -> spec.sslContext(http2SslContextSpec)) ②
                .handle((request, response) -> response.sendString(Mono
.just("hello")))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Configures the server to support only HTTP/2

② Configures SSL

The application should now behave as follows:

```
$ curl --http2 https://localhost:8080 -i
HTTP/2 200

hello
```

The following listing presents a simple H2C example:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/http2/H2CAApplication.java

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.HttpProtocol;
import reactor.netty.http.server.HttpServer;

public class H2CAApplication {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .port(8080)
                .protocol(HttpProtocol.H2C)
                .handle((request, response) -> response.sendString(Mono
.just("hello")))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

The application should now behave as follows:

```
$ curl --http2-prior-knowledge http://localhost:8080 -i
HTTP/2 200

hello
```

### 5.10.1. Protocol Selection

./../reactor-netty-http/src/main/java/reactor/netty/http/HttpProtocol.java

```
public enum HttpProtocol {

    /**
     * The default supported HTTP protocol by HttpServer and HttpClient
     */
    HTTP11,

    /**
     * HTTP/2.0 support with TLS
     * <p>If used along with HTTP/1.1 protocol, HTTP/2.0 will be the preferred
    protocol.
     * While negotiating the application level protocol, HTTP/2.0 or HTTP/1.1 can
    be chosen.
     * <p>If used without HTTP/1.1 protocol, HTTP/2.0 will always be offered as a
    protocol
     * for communication with no fallback to HTTP/1.1.
     */
    H2,

    /**
     * HTTP/2.0 support with clear-text.
     * <p>If used along with HTTP/1.1 protocol, will support H2C "upgrade":
     * Request or consume requests as HTTP/1.1 first, looking for HTTP/2.0 headers
     * and {@literal Connection: Upgrade}. A server will typically reply a
    successful
     * 101 status if upgrade is successful or a fallback HTTP/1.1 response. When
     * successful the client will start sending HTTP/2.0 traffic.
     * <p>If used without HTTP/1.1 protocol, will support H2C "prior-knowledge":
    Doesn't
     * require {@literal Connection: Upgrade} handshake between a client and
    server but
     * fallback to HTTP/1.1 will not be supported.
     */
    H2C
}
```

## 5.11. Metrics

The HTTP server supports built-in integration with **Micrometer**. It exposes all metrics with a prefix of **reactor.netty.http.server**.

The following table provides information for the HTTP server metrics:

metric name	type	description
reactor.netty.http.server.streams.active	Gauge	The number of active HTTP/2 streams. See <a href="#">Streams Active</a>
reactor.netty.http.server.connections.active	Gauge	The number of http connections currently processing requests. See <a href="#">Connections Active</a>
reactor.netty.http.server.connections.total	Gauge	The number of all opened connections. See <a href="#">Connections Total</a>
reactor.netty.http.server.data.received	DistributionSummary	Amount of the data received, in bytes. See <a href="#">Data Received</a>
reactor.netty.http.server.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.http.server.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>
reactor.netty.http.server.data.received.time	Timer	Time spent in consuming incoming data. See <a href="#">Http Server Data Received Time</a>
reactor.netty.http.server.data.sent.time	Timer	Time spent in sending outgoing data. See <a href="#">Http Server Data Sent Time</a>
reactor.netty.http.server.response.time	Timer	Total time for the request/response See <a href="#">Http Server Response Time</a>

These additional metrics are also available:

#### ByteBufAllocator metrics

metric name	type	description
reactor.netty.bytebuf.allocator.used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf.allocator.used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>
reactor.netty.bytebuf.allocator.heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf.allocator.direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>

metric name	type	description
reactor.netty.bytebuf allocator.threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf allocator.small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>
reactor.netty.bytebuf allocator.normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf allocator.chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>
reactor.netty.bytebuf allocator.active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf allocator.active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending.tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/metrics/Application.java

```
import io.micrometer.core.instrument.Metrics;
import io.micrometer.core.instrument.config.MeterFilter;
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        Metrics.globalRegistry ①
            .config()
            .meterFilter(MeterFilter.maximumAllowableTags
("reactor.netty.http.server", "URI", 100, MeterFilter.deny()));

        DisposableServer server =
            HttpServer.create()
                .metrics(true, s -> {
                    if (s.startsWith("/stream/")) { ②
                        return "/stream/{n}";
                    }
                    else if (s.startsWith("/bytes/")) {
                        return "/bytes/{n}";
                    }
                    return s;
                }) ③
                .route(r ->
                    r.get("/stream/{n}",
                        (req, res) -> res.sendString(Mono.just(req
.param("n")))))
                    .get("/bytes/{n}",
                        (req, res) -> res.sendString(Mono.just(req
.param("n")))))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

- ① Applies upper limit for the meters with URI tag
- ② Templated URIs will be used as an URI tag value when possible
- ③ Enables the built-in integration with Micrometer



In order to avoid a memory and CPU overhead of the enabled metrics, it is important to convert the real URIs to templated URIs when possible. Without a conversion to a template-like form, each distinct URI leads to the creation of a distinct tag, which takes a lot of memory for the metrics.



Always apply an upper limit for the meters with URI tags. Configuring an upper limit on the number of meters can help in cases when the real URIs cannot be templated. You can find more information at [maximumAllowableTags](#).

When HTTP server metrics are needed for an integration with a system other than [Micrometer](#) or you want to provide your own integration with [Micrometer](#), you can provide your own metrics recorder, as follows:

`./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/server/metrics/custom/Application  
n.java`

```
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;
import reactor.netty.http.server.HttpServerMetricsRecorder;

import java.net.SocketAddress;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .metrics(true, CustomHttpServerMetricsRecorder::new) ①
                .route(r ->
                    r.get("/stream/{n}",
                        (req, res) -> res.sendString(Mono.just(req
                            .param("n")))))
                    .get("/bytes/{n}",
                        (req, res) -> res.sendString(Mono.just(req
                            .param("n")))))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Enables HTTP server metrics and provides [HttpServerMetricsRecorder](#) implementation.



## 5.12. Tracing

The HTTP server supports built-in integration with **Micrometer Tracing**.

The following table provides information for the HTTP server spans:

contextual name	description
<HTTP METHOD>_<URI>	Information and total time for the request. See <a href="#">Http Server Response Span</a> .

The following example enables that integration. This concrete example uses **Brave** and reports the information to **Zipkin**. See the **Micrometer Tracing** documentation for **OpenTelemetry** setup.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/tracing/Application.java

```
import brave.Tracing;
import brave.handler.SpanHandler;
import brave.propagation.StrictCurrentTraceContext;
import brave.sampler.Sampler;
import io.micrometer.tracing.CurrentTraceContext;
import io.micrometer.tracing.Tracer;
import io.micrometer.tracing.brave.bridge.BraveBaggageManager;
import io.micrometer.tracing.brave.bridge.BraveCurrentTraceContext;
import io.micrometer.tracing.brave.bridge.BravePropagator;
import io.micrometer.tracing.brave.bridge.BraveTracer;
import io.micrometer.tracing.propagation.Propagator;
import reactor.core.publisher.Mono;
import reactor.netty.DisposableServer;
import
reactor.netty.http.observeability.ReactorNettyPropagatingReceiverTracingObservation
Handler;
import reactor.netty.http.server.HttpServer;
import zipkin2.reporter.AsyncReporter;
import zipkin2.reporter.brave.ZipkinSpanHandler;
import zipkin2.reporter.urlconnection.URLConnectionSender;

import static reactor.netty.Metrics.OBSERVATION_REGISTRY;

public class Application {

    public static void main(String[] args) {
        init(); ①

        DisposableServer server =
            HttpServer.create()
                .metrics(true, s -> {
                    if (s.startsWith("/stream/")) { ②
                        return "/stream/{n}";
                    }
                    return s;
                }) ③
                .route(r -> r.get("/stream/{n}",
                    (req, res) -> res.sendString(Mono.just(req.param(
                        "n")))))
                .bindNow();

        server.onDispose()
            .block();
    }

    /**
     * This setup is based on
```

```

* <a
href="https://micrometer.io/docs/tracing#_micrometer_tracing_brave_setup">Micromet
er Tracing Brave Setup</a>
*/
static void init() {
    SpanHandler spanHandler = ZipkinSpanHandler
        .create(AsyncReporter.create(URLConnectionSender.create
("http://localhost:9411/api/v2/spans"))));

    StrictCurrentTraceContext braveCurrentTraceContext =
StrictCurrentTraceContext.create();

    CurrentTraceContext bridgeContext = new BraveCurrentTraceContext
(braveCurrentTraceContext);

    Tracing tracing =
        Tracing.newBuilder()
            .currentTraceContext(braveCurrentTraceContext)
            .supportsJoin(false)
            .traceId128Bit(true)
            .sampler(Sampler.ALWAYS_SAMPLE)
            .addSpanHandler(spanHandler)
            .localServiceName("reactor-netty-examples")
            .build();

    brave.Tracer braveTracer = tracing.tracer();

    Tracer tracer = new BraveTracer(braveTracer, bridgeContext, new
BraveBaggageManager());

    Propagator propagator = new BravePropagator(tracing);

    OBSERVATION_REGISTRY.observationConfig()
        .observationHandler(new
ReactorNettyPropagatingReceiverTracingObservationHandler(tracer, propagator));
}
}

```

- ① Initializes Brave, Zipkin, and the Observation registry.
- ② Templated URIs are used as an URI tag value when possible.
- ③ Enables the built-in integration with Micrometer.

The result in Zipkin looks like:

## REACTOR-NETTY-EXAMPLES

get\_stream/{n}

Span ID: 28c84d85abfb0c93 Parent ID: 20d5d8026247f238

### Annotations



SHOW ALL ANNOTATIONS

### Tags

http.scheme	http
http.status_code	200
net.host.name	127.0.0.1
net.host.port	8080
reactor.netty.type	server

## 5.13. Unix Domain Sockets

The **HTTP** server supports Unix Domain Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/server/uds/Application.java

```
import io.netty.channel.unix.DomainSocketAddress;
import reactor.netty.DisposableServer;
import reactor.netty.http.server.HttpServer;

public class Application {

    public static void main(String[] args) {
        DisposableServer server =
            HttpServer.create()
                .bindAddress(() -> new DomainSocketAddress
("/tmp/test.sock")) ①
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Specifies `DomainSocketAddress` that will be used

# Chapter 6. HTTP Client

Reactor Netty provides the easy-to-use and easy-to-configure `HttpClient`. It hides most of the Netty functionality that is required to create an `HTTP` client and adds Reactive Streams backpressure.

## 6.1. Connect

To connect the `HTTP` client to a given `HTTP` endpoint, you must create and configure a `HttpClient` instance. The following example shows how to do so:

`./../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/http/client/connect/Application.java`

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create(); ①

        client.get()                             ②
            .uri("https://example.com/") ③
            .response()                         ④
            .block();

    }
}
```

- ① Creates a `HttpClient` instance ready for configuring.
- ② Specifies that `GET` method will be used.
- ③ Specifies the path.
- ④ Obtains the response `HttpClientResponse`

The following example uses `WebSocket`:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/websocket/Application.java

```
import io.netty.buffer.Unpooled;
import io.netty.util.CharsetUtil;
import reactor.core.publisher.Flux;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create();

        client.websocket()
            .uri("wss://echo.websocket.org")
            .handle((inbound, outbound) -> {
                inbound.receive()
                    .asString()
                    .take(1)
                    .subscribe(System.out::println);

                final byte[] msgBytes = "hello".getBytes(CharsetUtil.
ISO_8859_1);
                return outbound.send(Flux.just(Unpooled.wrappedBuffer(msgBytes),
Unpooled.wrappedBuffer(msgBytes)))
                    .neverComplete();
            })
            .blockLast();
    }
}
```

### 6.1.1. Host and Port

In order to connect to a specific host and port, you can apply the following configuration to the **HTTP** client:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/address/Application.java

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .host("example.com") ①
                .port(80);           ②

        client.get()
            .uri("/")
            .response()
            .block();
    }
}
```

① Configures the **HTTP** host

② Configures the **HTTP** port

## 6.2. Eager Initialization

By default, the initialization of the **HttpClient** resources happens on demand. This means that the **first request** absorbs the extra time needed to initialize and load:

- the event loop group
- the host name resolver
- the native transport libraries (when native transport is used)
- the native libraries for the security (in case of **OpenSsl**)

When you need to preload these resources, you can configure the **HttpClient** as follows:



../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/warmup/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.ByteBufFlux;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create();

        client.warmup() ①
            .block();

        client.post()
            .uri("https://example.com/")
            .send(ByteBufFlux.fromString(Mono.just("hello")))
            .response()
            .block(); ②
    }
}
```

- ① Initialize and load the event loop group, the host name resolver, the native transport libraries and the native libraries for the security
- ② Host name resolution happens with the first request. In this example, a connection pool is used, so with the first request the connection to the URL is established, the subsequent requests to the same URL reuse the connections from the pool.

## 6.3. Writing Data

To send data to a given **HTTP** endpoint, you can provide a **Publisher** by using the `send(Publisher)` method. By default, **Transfer-Encoding: chunked** is applied for those **HTTP** methods for which a request body is expected. **Content-Length** provided through request headers disables **Transfer-Encoding: chunked**, if necessary. The following example sends **hello**:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/send/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.ByteBufFlux;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create();

        client.post()
            .uri("https://example.com/")
            .send(ByteBufFlux.fromString(Mono.just("hello"))) ①
            .response()
            .block();
    }
}
```

① Sends a `hello` string to the given `HTTP` endpoint

### 6.3.1. Adding Headers and Other Metadata

When sending data to a given `HTTP` endpoint, you may need to send additional headers, cookies and other metadata. You can use the following configuration to do so:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/send/headers/Application.java

```
import io.netty.handler.codec.http.HttpHeaderNames;
import reactor.core.publisher.Mono;
import reactor.netty.ByteBufFlux;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .headers(h -> h.set(HttpHeaderNames.CONTENT_LENGTH, 5));
        ①

        client.post()
            .uri("https://example.com/")
            .send(ByteBufFlux.fromString(Mono.just("hello")))
            .response()
            .block();
    }
}
```

① Disables **Transfer-Encoding: chunked** and provides **Content-Length** header.

## Compression

You can enable compression on the **HTTP** client, which means the request header **Accept-Encoding** is added to the request headers. The following example shows how to do so:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/compression/Application.java
```

```
import reactor.netty.http.client.HttpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .compress(true);  
  
        client.get()  
            .uri("https://example.com/")  
            .response()  
            .block();  
    }  
}
```

## Auto-Redirect Support

You can configure the **HTTP** client to enable auto-redirect support.

Reactor Netty provides two different strategies for auto-redirect support:

- `followRedirect(boolean)`: Specifies whether HTTP auto-redirect support is enabled for statuses `301|302|303|307|308`. When it is `303` status code, `GET` method is used for the redirect.
- `followRedirect(BiPredicate<HttpClientRequest, HttpClientResponse>)`: Enables auto-redirect support if the supplied predicate matches.

The following example uses `followRedirect(true)`:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/redirect/Application.java

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .followRedirect(true);

        client.get()
            .uri("https://example.com/")
            .response()
            .block();
    }
}
```

## 6.4. Consuming Data

To receive data from a given **HTTP** endpoint, you can use one of the methods from **HttpClient.ResponseReceiver**. The following example uses the **responseContent** method:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/read/Application.java

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create();

        client.get()
            .uri("https://example.com/")
            .responseContent() ①
            .aggregate()       ②
            .asString()        ③
            .block();
    }
}
```

- ① Receives data from a given **HTTP** endpoint
- ② Aggregates the data
- ③ Transforms the data as string

### 6.4.1. Reading Headers and Other Metadata

When receiving data from a given **HTTP** endpoint, you can check response headers, status code, and other metadata. You can obtain this additional metadata by using **HttpClientResponse**. The following example shows how to do so.

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/read/status/Application.java

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client = HttpClient.create();

        client.get()
            .uri("https://example.com/")
            .responseSingle((resp, bytes) -> {
                System.out.println(resp.status()); ①
                return bytes.asString();
            })
            .block();
    }
}
```

① Obtains the status code.

### 6.4.2. HTTP Response Decoder

By default, **Netty** configures some restrictions for the incoming responses, such as:

- The maximum length of the initial line.
- The maximum length of all headers.
- The maximum length of the content or each chunk.

For more information, see [HttpResponseDecoder](#)

By default, the **HTTP** client is configured with the following settings:

*../../reactor-netty-http/src/main/java/reactor/netty/http/HttpDecoderSpec.java*

```
public static final int DEFAULT_MAX_INITIAL_LINE_LENGTH           = 4096;
public static final int DEFAULT_MAX_HEADER_SIZE                  = 8192;
/**
 * @deprecated as of 1.1.0. This will be removed in 2.0.0 as Netty 5 does not
 * support this configuration.
 */
@Deprecated
public static final int DEFAULT_MAX_CHUNK_SIZE                   = 8192;
public static final boolean DEFAULT_VALIDATE_HEADERS             = true;
public static final int DEFAULT_INITIAL_BUFFER_SIZE              = 128;
public static final boolean DEFAULT_ALLOW_DUPLICATE_CONTENT_LENGTHS = false;
```

*../../reactor-netty-http/src/main/java/reactor/netty/http/client/HttpResponseDecoderSpec.java*

```
public static final boolean DEFAULT_FAIL_ON_MISSING_RESPONSE      = false;
public static final boolean DEFAULT_PARSE_HTTP_AFTER_CONNECT_REQUEST = false;

/**
 * The maximum length of the content of the HTTP/2.0 clear-text upgrade request.
 * By default, the client will allow an upgrade request with up to 65536 as
 * the maximum length of the aggregated content.
 */
public static final int DEFAULT_H2C_MAX_CONTENT_LENGTH = 65536;
```

When you need to change these default settings, you can configure the **HTTP** client as follows:



```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/responsedecoder/Application.  
n.java
```

```
import reactor.netty.http.client.HttpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .httpResponseDecoder(spec -> spec.maxHeaderSize(16384));  
  
        ①  
  
        client.get()  
            .uri("https://example.com/")  
            .responseContent()  
            .aggregate()  
            .asString()  
            .block();  
    }  
}
```

① The maximum length of all headers will be 16384. When this value is exceeded, a `TooLongFrameException` is raised.

## 6.5. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `HttpClient`.

Callback	Description
<code>doAfterRequest</code>	Invoked when the request has been sent.
<code>doAfterResolve</code>	Invoked after the remote address has been resolved successfully.
<code>doAfterResponseSuccess</code>	Invoked after the response has been fully received.
<code>doOnChannelInit</code>	Invoked when initializing the channel.
<code>doOnConnect</code>	Invoked when the channel is about to connect.
<code>doOnConnected</code>	Invoked after the channel has been connected.
<code>doOnDisconnected</code>	Invoked after the channel has been disconnected.
<code>doOnError</code>	Invoked when the request has not been sent and when the response has not been fully received.

Callback	Description
<code>doOnRedirect</code>	Invoked when the response headers have been received, and the request is about to be redirected.
<code>doOnRequest</code>	Invoked when the request is about to be sent.
<code>doOnRequestError</code>	Invoked when the request has not been sent.
<code>doOnResolve</code>	Invoked when the remote address is about to be resolved.
<code>doOnResolveError</code>	Invoked in case the remote address hasn't been resolved successfully.
<code>doOnResponse</code>	Invoked after the response headers have been received.
<code>doOnResponseError</code>	Invoked when the response has not been fully received.

The following example uses the `doOnConnected` and `doOnChannelInit` callbacks:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/lifecycle/Application.java

```
import io.netty.handler.logging.LoggingHandler;
import io.netty.handler.timeout.ReadTimeoutHandler;
import reactor.netty.http.client.HttpClient;
import java.util.concurrent.TimeUnit;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .doOnConnected(conn ->
                    conn.addHandlerFirst(new ReadTimeoutHandler(10,
TimeUnit.SECONDS))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))); ②

        client.get()
            .uri("https://example.com/")
            .response()
            .block();
    }
}
```

① Netty pipeline is extended with `ReadTimeoutHandler` when the channel has been connected.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 6.6. TCP-level Configuration

When you need configurations on a TCP level, you can use the following snippet to extend the default TCP client configuration (add an option, bind address etc.):

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/channeloptions/Application  
.java

```
import io.netty.channel.ChannelOption;
import io.netty.channel.epoll.EpollChannelOption;
//import io.netty.channel.socket.nio.NioChannelOption;
//import jdk.net.ExtendedSocketOptions;
import reactor.netty.http.client.HttpClient;
import java.net.InetSocketAddress;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .bindAddress(() -> new InetSocketAddress("host", 1234))
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000) ①
                .option(ChannelOption.SO_KEEPALIVE, true) ②
                // The options below are available only when NIO
transport (Java 11) is used
                // on Mac or Linux (Java does not currently support
these extended options on Windows)
                // https://bugs.openjdk.java.net/browse/JDK-8194298

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPIDLE), 300)

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPINTERVAL), 60)

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPCOUNT), 8);
                // The options below are available only when Epoll
transport is used
                .option(EpollChannelOption.TCP_KEEPIDLE, 300) ③
                .option(EpollChannelOption.TCP_KEEPINTVL, 60) ④
                .option(EpollChannelOption.TCP_KEEPCNT, 8); ⑤

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① Configures the connection establishment timeout to 10 seconds.

- ② Enables TCP **keepalive**. This means that TCP starts sending **keepalive** probes when a connection is idle for some time.
- ③ The connection needs to remain idle for 5 minutes before TCP starts sending **keepalive** probes.
- ④ Configures the time between individual **keepalive** probes to 1 minute.
- ⑤ Configures the maximum number of TCP **keepalive** probes to 8.

See [TCP Client](#) for more about **TCP** level configurations.

### 6.6.1. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected. By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.http.client.HttpClient` level to **DEBUG** and apply the following configuration:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/wiretap/Application.java
```

```
import reactor.netty.http.client.HttpClient;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .wiretap(true); ①  
  
        client.get()  
            .uri("https://example.com/")  
            .response()  
            .block();  
    }  
}
```

- ① Enables the wire logging

### Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

*./../reactor-netty-http/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java*

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

*./../reactor-netty-http/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java*

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/wiretap/custom/Application  
.java
```

```
import io.netty.handler.logging.LogLevel;  
import reactor.netty.http.client.HttpClient;  
import reactor.netty.transport.logging.AdvancedByteBufFormat;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .wiretap("logger-name", LogLevel.DEBUG,  
AdvancedByteBufFormat.TEXTUAL); ①  
  
        client.get()  
            .uri("https://example.com/")  
            .response()  
            .block();  
    }  
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

## 6.7. Connection Pool

By default, `HttpClient` uses a “fixed” connection pool with `500` as the maximum number of active channels and `1000` as the maximum number of further channel acquisition attempts allowed to be kept in a pending state (for the rest of the configurations check the system properties or the builder configurations below). This means that the implementation creates a new channel if someone tries to acquire a channel as long as less than `500` have been created and are managed by the pool. When the maximum number of channels in the pool is reached, up to `1000` new attempts to acquire a channel are delayed (pending) until a channel is returned to the pool again, and further attempts are declined with an error.



./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java

```
/**
 * Default max connections. Fallback to
 * 2 * available number of processors (but with a minimum value of 16)
 */
public static final String POOL_MAX_CONNECTIONS =
"reactor.netty.pool.maxConnections";
/**
 * Default acquisition timeout (milliseconds) before error. If -1 will never wait
 to
 * acquire before opening a new
 * connection in an unbounded fashion. Fallback 45 seconds
 */
public static final String POOL_ACQUIRE_TIMEOUT =
"reactor.netty.pool.acquireTimeout";
/**
 * Default max idle time, fallback - max idle time is not specified.
 * <p><strong>Note:</strong> This configuration is not applicable for {@link
 reactor.netty.tcp.TcpClient}.
 * A TCP connection is always closed and never returned to the pool.
 */
public static final String POOL_MAX_IDLE_TIME = "reactor.netty.pool.maxIdleTime";
/**
 * Default max life time, fallback - max life time is not specified.
 * <p><strong>Note:</strong> This configuration is not applicable for {@link
 reactor.netty.tcp.TcpClient}.
 * A TCP connection is always closed and never returned to the pool.
 */
public static final String POOL_MAX_LIFE_TIME = "reactor.netty.pool.maxLifeTime";
/**
 * Default leasing strategy (fifo, lifo), fallback to fifo.
 * <ul>
 * <li>fifo - The connection selection is first in, first out</li>
 * <li>lifo - The connection selection is last in, first out</li>
 * </ul>
 * <p><strong>Note:</strong> This configuration is not applicable for {@link
 reactor.netty.tcp.TcpClient}.
 * A TCP connection is always closed and never returned to the pool.
 */
public static final String POOL_LEASING_STRATEGY =
"reactor.netty.pool.leasingStrategy";
/**
 * Default {@code getPermitsSamplingRate} (between 0d and 1d (percentage))
 * to be used with a {@link SamplingAllocationStrategy}.
 * This strategy wraps a {@link PoolBuilder#sizeBetween(int, int) sizeBetween}
 {@link AllocationStrategy}
 * and samples calls to {@link AllocationStrategy#getPermits(int)}.
 * Fallback - sampling is not enabled.
 */
```

```

public static final String POOL_GET_PERMITS_SAMPLING_RATE =
    "reactor.netty.pool.getPermitsSamplingRate";
/**
 * Default {@code returnPermitsSamplingRate} (between 0d and 1d (percentage))
 * to be used with a {@link SamplingAllocationStrategy}.
 * This strategy wraps a {@link PoolBuilder#sizeBetween(int, int) sizeBetween}
 * {@link AllocationStrategy}
 * and samples calls to {@link AllocationStrategy#returnPermits(int)}.
 * Fallback - sampling is not enabled.
 */
public static final String POOL_RETURN_PERMITS_SAMPLING_RATE =
    "reactor.netty.pool.returnPermitsSamplingRate";

```

When you need to change the default settings, you can configure the `ConnectionProvider` as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/pool/config/Application.java

```
import reactor.netty.http.client.HttpClient;
import reactor.netty.resources.ConnectionProvider;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        ConnectionProvider provider =
            ConnectionProvider.builder("custom")
                .maxConnections(50)
                .maxIdleTime(Duration.ofSeconds(20))
                .maxLifeTime(Duration.ofSeconds(60))
                .pendingAcquireTimeout(Duration.ofSeconds(60))
                .evictInBackground(Duration.ofSeconds(120))
                .build();

        HttpClient client = HttpClient.create(provider);

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);

        provider.disposeLater()
            .block();
    }
}
```

- ① Configures the maximum time for a connection to stay idle to 20 seconds.
- ② Configures the maximum time for a connection to stay alive to 60 seconds.
- ③ Configures the maximum time for the pending acquire operation to 60 seconds.
- ④ Every two minutes, the connection pool is regularly checked for connections that are applicable for removal.



Notice that only the default `HttpClient` (`HttpClient.create()`) uses `500` as the maximum number of active channels. In the example above, when instantiating a custom `ConnectionProvider`, we are changing this value to `50` using `maxConnections`. Also, if you don't set this parameter the default `maxConnections` is used (`2 * available number of processors`).

The following listing shows the available configurations:

Configuration name	Description
<code>disposeInactivePoolsInBackground</code>	When this option is enabled, connection pools are regularly checked in the background, and those that are empty and been inactive for a specified time become eligible for disposal. By default, this background disposal of inactive pools is disabled.
<code>disposeTimeout</code>	When <code>ConnectionProvider#dispose()</code> or <code>ConnectionProvider#disposeLater()</code> is called, trigger a graceful shutdown for the connection pools, with this grace period timeout. From there on, all calls for acquiring a connection will fail fast with an exception. However, for the provided <code>Duration</code> , pending acquires will get a chance to be served. Note: The rejection of new acquires and the grace timer start immediately, irrespective of subscription to the <code>Mono</code> returned by <code>ConnectionProvider#disposeLater()</code> . Subsequent calls return the same <code>Mono</code> , effectively getting notifications from the first graceful shutdown call and ignoring subsequently provided timeouts. By default, dispose timeout is not specified.
<code>evictInBackground</code>	When this option is enabled, each connection pool regularly checks for connections that are eligible for removal according to eviction criteria like <code>maxIdleTime</code> . By default, this background eviction is disabled.
<code>fifo</code>	Configure the connection pool so that if there are idle connections (i.e. pool is under-utilized), the next acquire operation will get the <code>Least Recently Used</code> connection (LRU, i.e. the connection that was released first among the current idle connections). Default leasing strategy.

Configuration name	Description
<code>lifo</code>	Configure the connection pool so that if there are idle connections (i.e. pool is under-utilized), the next acquire operation will get the <b>Most Recently Used</b> connection (MRU, i.e. the connection that was released last among the current idle connections).
<code>maxConnections</code>	The maximum number of connections (per connection pool) before start pending. Default to 2 * available number of processors (but with a minimum value of 16).
<code>maxIdleTime</code>	The time after which the channel is eligible to be closed when idle (resolution: ms). Default: max idle time is not specified.
<code>maxLifeTime</code>	The total life time after which the channel is eligible to be closed (resolution: ms). Default: max life time is not specified.
<code>metrics</code>	Enables/disables built-in integration with Micrometer. <code>ConnectionProvider.MeterRegistrar</code> can be provided for integration with another metrics system. By default, metrics are not enabled.
<code>pendingAcquireMaxCount</code>	The maximum number of extra attempts at acquiring a connection to keep in a pending queue. If -1 is specified, the pending queue does not have upper limit. Default to 2 * max connections.
<code>pendingAcquireTimeout</code>	The maximum time before which a pending acquire must complete, or a <code>TimeoutException</code> is thrown (resolution: ms). If -1 is specified, no such timeout is applied. Default: 45 seconds.



When you expect a high load, be cautious with a connection pool with a very high value for maximum connections. You might experience `reactor.netty.http.client.PrematureCloseException` exception with a root cause "Connect Timeout" due to too many concurrent connections opened/acquired.

If you need to disable the connection pool, you can apply the following configuration:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/pool/Application.java

```
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.newConnection()
                .doOnConnected(conn -> System.out.println("Connection "
+ conn.channel()));

        String response =
            // A new connection is established for every request
            client.get()
                .uri("https://httpbin.org/get")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);

        response =
            // A new connection is established for every request
            client.post()
                .uri("https://httpbin.org/post")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

### 6.7.1. Metrics

The pooled `ConnectionProvider` supports built-in integration with `Micrometer`. It exposes all metrics with a prefix of `reactor.netty.connection.provider`.

Pooled `ConnectionProvider` metrics

metric name	type	description
reactor.netty.connection.provider.total.connections	Gauge	The number of all connections, active or idle. See <a href="#">Total Connections</a>
reactor.netty.connection.provider.active.connections	Gauge	The number of the connections that have been successfully acquired and are in active use. See <a href="#">Active Connections</a>
reactor.netty.connection.provider.max.connections	Gauge	The maximum number of active connections that are allowed. See <a href="#">Max Connections</a>
reactor.netty.connection.provider.idle.connections	Gauge	The number of the idle connections. See <a href="#">Idle Connections</a>
reactor.netty.connection.provider.pending.connections	Gauge	The number of requests that are waiting for a connection. See <a href="#">Pending Connections</a>
reactor.netty.connection.provider.max.pending.connections	Gauge	The maximum number of requests that will be queued while waiting for a ready connection. See <a href="#">Max Pending Connections</a>

The following example enables that integration:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/pool/metrics/Application.java
```

```
import reactor.netty.http.client.HttpClient;  
import reactor.netty.resources.ConnectionProvider;  
  
public class Application {  
  
    public static void main(String[] args) {  
        ConnectionProvider provider =  
            ConnectionProvider.builder("custom")  
                .maxConnections(50)  
                .metrics(true) ①  
                .build();  
  
        HttpClient client = HttpClient.create(provider);  
  
        String response =  
            client.get()  
                .uri("https://example.com/")  
                .responseContent()  
                .aggregate()  
                .asString()  
                .block();  
  
        System.out.println("Response " + response);  
  
        provider.disposeLater()  
            .block();  
    }  
}
```

① Enables the built-in integration with Micrometer

## 6.8. SSL and TLS

When you need SSL or TLS, you can apply the configuration shown in the next example. By default, if `OpenSSL` is available, a `SslProvider.OPENSSL` provider is used as a provider. Otherwise, a `SslProvider.JDK` provider is used. You can switch the provider by using `SslContextBuilder` or by setting `-Dio.netty.handler.ssl.noOpenSsl=true`. The following example uses `SslContextBuilder`:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/security/Application.java

```
import reactor.netty.http.Http11SslContextSpec;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        Http11SslContextSpec http11SslContextSpec = Http11SslContextSpec.
forClient();

        HttpClient client =
            HttpClient.create()
                .secure(spec -> spec.sslContext(http11SslContextSpec));

        client.get()
            .uri("https://example.com/")
            .response()
            .block();
    }
}
```

### 6.8.1. Server Name Indication

By default, the **HTTP** client sends the remote host name as **SNI** server name. When you need to change this default setting, you can configure the **HTTP** client as follows:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/sni/Application.java
```

```
import io.netty.handler.ssl.SslContext;  
import io.netty.handler.ssl.SslContextBuilder;  
import reactor.netty.http.client.HttpClient;  
  
import javax.net.ssl.SNIHostName;  
  
public class Application {  
  
    public static void main(String[] args) throws Exception {  
        SslContext sslContext = SslContextBuilder.forClient().build();  
  
        HttpClient client =  
            HttpClient.create()  
                .secure(spec -> spec.sslContext(sslContext)  
                    .serverNames(new SNIHostName  
("test.com")));  
  
        client.get()  
            .uri("https://127.0.0.1:8080/")  
            .response()  
            .block();  
    }  
}
```

## 6.9. Retry Strategies

By default, the **HTTP** client retries the request once if it was aborted on the **TCP** level.

## 6.10. HTTP/2

By default, the **HTTP** client supports **HTTP/1.1**. If you need **HTTP/2**, you can get it through configuration. In addition to the protocol configuration, if you need **H2** but not **H2C (cleartext)**, you must also configure SSL.



As Application-Layer Protocol Negotiation (ALPN) is not supported “out-of-the-box” by JDK8 (although some vendors backported ALPN to JDK8), you need an additional dependency to a native library that supports it—for example, `netty-tcnative-boringssl-static`.

The following listing presents a simple **H2** example:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/http2/H2Application.java

```
import io.netty.handler.codec.http.HttpHeaders;
import reactor.core.publisher.Mono;
import reactor.netty.http.HttpProtocol;
import reactor.netty.http.client.HttpClient;
import reactor.util.function.Tuple2;

public class H2Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .protocol(HttpProtocol.H2) ①
                .secure();                 ②

        Tuple2<String, HttpHeaders> response =
            client.get()
                .uri("https://example.com/")
                .responseSingle((res, bytes) -> bytes.asString()
                    .zipWith(Mono.just(res
                        .responseHeaders()))))
                .block();

        System.out.println("Used stream ID: " + response.getT2().get("x-http2-
stream-id"));
        System.out.println("Response: " + response.getT1());
    }
}
```

① Configures the client to support only HTTP/2

② Configures SSL

The following listing presents a simple H2C example:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/http2/H2CApplication.java

```
import io.netty.handler.codec.http.HttpHeaders;
import reactor.core.publisher.Mono;
import reactor.netty.http.HttpProtocol;
import reactor.netty.http.client.HttpClient;
import reactor.util.function.Tuple2;

public class H2CApplication {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .protocol(HttpProtocol.H2C);

        Tuple2<String, HttpHeaders> response =
            client.get()
                .uri("http://localhost:8080/")
                .responseSingle((res, bytes) -> bytes.asString()
                    .zipWith(Mono.just(res
                        .responseHeaders()))))
                .block();

        System.out.println("Used stream ID: " + response.getT2().get("x-http2-
stream-id"));
        System.out.println("Response: " + response.getT1());
    }
}
```

### 6.10.1. Protocol Selection

./../reactor-netty-http/src/main/java/reactor/netty/http/HttpProtocol.java

```
public enum HttpProtocol {

    /**
     * The default supported HTTP protocol by HttpServer and HttpClient
     */
    HTTP11,

    /**
     * HTTP/2.0 support with TLS
     * <p>If used along with HTTP/1.1 protocol, HTTP/2.0 will be the preferred
    protocol.
     * While negotiating the application level protocol, HTTP/2.0 or HTTP/1.1 can
    be chosen.
     * <p>If used without HTTP/1.1 protocol, HTTP/2.0 will always be offered as a
    protocol
     * for communication with no fallback to HTTP/1.1.
     */
    H2,

    /**
     * HTTP/2.0 support with clear-text.
     * <p>If used along with HTTP/1.1 protocol, will support H2C "upgrade":
     * Request or consume requests as HTTP/1.1 first, looking for HTTP/2.0 headers
     * and {@literal Connection: Upgrade}. A server will typically reply a
    successful
     * 101 status if upgrade is successful or a fallback HTTP/1.1 response. When
     * successful the client will start sending HTTP/2.0 traffic.
     * <p>If used without HTTP/1.1 protocol, will support H2C "prior-knowledge":
    Doesn't
     * require {@literal Connection: Upgrade} handshake between a client and
    server but
     * fallback to HTTP/1.1 will not be supported.
     */
    H2C
}
```

## 6.11. Proxy Support

Reactor Netty supports the proxy functionality provided by Netty and provides a way to specify **non proxy hosts** through the **ProxyProvider** builder.

Netty's HTTP proxy support always uses **CONNECT** method in order to establish a tunnel to the specified proxy regardless of the scheme that is used **http** or **https**. (More information: [Netty enforce HTTP proxy to support HTTP CONNECT method](#)). Some proxies might not support **CONNECT** method when the scheme is **http** or might need to be configured in order to support this way of communication. Sometimes this might be the reason for not being able to connect to the proxy.

Consider checking the proxy documentation whether it supports or needs an additional configuration in order to support **CONNECT** method.

The following example uses **ProxyProvider**:

`../../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/http/client/proxy/Application.java`

```
import reactor.netty.http.client.HttpClient;
import reactor.netty.transport.ProxyProvider;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .proxy(spec -> spec.type(ProxyProvider.Proxy.HTTP)
                    .host("proxy")
                    .port(8080)
                    .nonProxyHosts("localhost")
                    .connectTimeoutMillis(20_000)); ①

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① Configures the connection establishment timeout to 20 seconds.

## 6.12. Metrics

The HTTP client supports built-in integration with **Micrometer**. It exposes all metrics with a prefix of `reactor.netty.http.client`.

The following table provides information for the HTTP client metrics:

metric name	type	description
<code>reactor.netty.http.client.data.received</code>	<code>DistributionSummary</code>	Amount of the data received, in bytes. See <a href="#">Data Received</a>

metric name	type	description
reactor.netty.http.client.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.http.client.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>
reactor.netty.http.client.tls.handshake.time	Timer	Time spent for TLS handshake. See <a href="#">Tls Handshake Time</a>
reactor.netty.http.client.connect.time	Timer	Time spent for connecting to the remote address. See <a href="#">Connect Time</a>
reactor.netty.http.client.address.resolver	Timer	Time spent for resolving the address. See <a href="#">Hostname Resolution Time</a>
reactor.netty.http.client.data.received.time	Timer	Time spent in consuming incoming data. See <a href="#">Http Client Data Received Time</a>
reactor.netty.http.client.data.sent.time	Timer	Time spent in sending outgoing data. See <a href="#">Http Client Data Sent Time</a>
reactor.netty.http.client.response.time	Timer	Total time for the request/response See <a href="#">Http Client Response Time</a>

These additional metrics are also available:

Pooled [ConnectionProvider](#) metrics

metric name	type	description
reactor.netty.connection.provider.total.connections	Gauge	The number of all connections, active or idle. See <a href="#">Total Connections</a>
reactor.netty.connection.provider.active.connections	Gauge	The number of the connections that have been successfully acquired and are in active use. See <a href="#">Active Connections</a>
reactor.netty.connection.provider.max.connections	Gauge	The maximum number of active connections that are allowed. See <a href="#">Max Connections</a>
reactor.netty.connection.provider.idle.connections	Gauge	The number of the idle connections. See <a href="#">Idle Connections</a>

metric name	type	description
reactor.netty.connection.provider.pending.connections	Gauge	The number of requests that are waiting for a connection. See <a href="#">Pending Connections</a>
reactor.netty.connection.provider.max.pending.connections	Gauge	The maximum number of requests that will be queued while waiting for a ready connection. See <a href="#">Max Pending Connections</a>

The following table provides information for the HTTP client metrics when it is configured to serve [HTTP/2](#) traffic:

metric name	type	description
reactor.netty.connection.provider.active.streams	Gauge	The number of the active HTTP/2 streams. See <a href="#">Active Streams</a>
reactor.netty.connection.provider.pending.streams	Gauge	The number of requests that are waiting for opening HTTP/2 stream. See <a href="#">Pending Streams</a>

#### [ByteBufAllocator](#) metrics

metric name	type	description
reactor.netty.bytebuf.allocator.used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf.allocator.used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>
reactor.netty.bytebuf.allocator.heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf.allocator.direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>
reactor.netty.bytebuf.allocator.threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf.allocator.small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>



metric name	type	description
reactor.netty.bytebuf allocator.normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf allocator.chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>
reactor.netty.bytebuf allocator.active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf allocator.active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending.tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/metrics/Application.java

```
import io.micrometer.core.instrument.Metrics;
import io.micrometer.core.instrument.config.MeterFilter;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        Metrics.globalRegistry ①
            .config()
            .meterFilter(MeterFilter.maximumAllowableTags
("reactor.netty.http.client", "URI", 100, MeterFilter.deny()));

        HttpClient client =
            HttpClient.create()
                .metrics(true, s -> {
                    if (s.startsWith("/stream/")) { ②
                        return "/stream/{n}";
                    }
                    else if (s.startsWith("/bytes/")) {
                        return "/bytes/{n}";
                    }
                    return s;
                }); ③

        client.get()
            .uri("https://httpbin.org/stream/2")
            .responseContent()
            .blockLast();

        client.get()
            .uri("https://httpbin.org/bytes/1024")
            .responseContent()
            .blockLast();
    }
}
```

- ① Applies upper limit for the meters with URI tag
- ② Templated URIs will be used as a URI tag value when possible
- ③ Enables the built-in integration with Micrometer



In order to avoid a memory and CPU overhead of the enabled metrics, it is important to convert the real URIs to templated URIs when possible. Without a conversion to a template-like form, each distinct URI leads to the creation of a distinct tag, which takes a lot of memory for the metrics.



Always apply an upper limit for the meters with URI tags. Configuring an upper limit on the number of meters can help in cases when the real URIs cannot be templated. You can find more information at [maximumAllowableTags](#).

When HTTP client metrics are needed for an integration with a system other than [Micrometer](#) or you want to provide your own integration with [Micrometer](#), you can provide your own metrics recorder, as follows:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/metrics/custom/Application  
.java
```

```
import reactor.netty.http.client.HttpClient;  
import reactor.netty.http.client.HttpClientMetricsRecorder;  
  
import java.net.SocketAddress;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .metrics(true, CustomHttpClientMetricsRecorder::new); ①  
  
        client.get()  
            .uri("https://httpbin.org/stream/2")  
            .response()  
            .block();  
    }  
}
```

① Enables HTTP client metrics and provides [HttpClientMetricsRecorder](#) implementation.

## 6.13. Tracing

The HTTP client supports built-in integration with [Micrometer Tracing](#).

The following table provides information for the HTTP client spans:

contextual name	description
HTTP <HTTP METHOD>	Information and total time for the request. See <a href="#">Http Client Response Span</a> .
hostname resolution	Information and time spent for resolving the address. See <a href="#">Hostname Resolution Span</a> .
connect	Information and time spent for connecting to the remote address. See <a href="#">Connect Span</a> .

contextual name	description
tls handshake	Information and time spent for TLS handshake. See <a href="#">Tls Handshake Span</a> .

The following example enables that integration. This concrete example uses **Brave** and reports the information to **Zipkin**. See the **Micrometer Tracing** documentation for **OpenTelemetry** setup.

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/tracing/Application.java

```
import brave.Tracing;
import brave.handler.SpanHandler;
import brave.propagation.StrictCurrentTraceContext;
import brave.sampler.Sampler;
import io.micrometer.tracing.CurrentTraceContext;
import io.micrometer.tracing.Tracer;
import io.micrometer.tracing.brave.bridge.BraveBaggageManager;
import io.micrometer.tracing.brave.bridge.BraveCurrentTraceContext;
import io.micrometer.tracing.brave.bridge.BravePropagator;
import io.micrometer.tracing.brave.bridge.BraveTracer;
import io.micrometer.tracing.propagation.Propagator;
import reactor.netty.http.client.HttpClient;
import reactor.netty.http observability.ReactorNettyPropagatingSenderTracingObservationHandler;
import reactor.netty.observability.ReactorNettyTracingObservationHandler;
import zipkin2.reporter.AsyncReporter;
import zipkin2.reporter.brave.ZipkinSpanHandler;
import zipkin2.reporter.urlconnection.URLConnectionSender;

import static reactor.netty.Metrics.OBSERVATION_REGISTRY;

public class Application {

    public static void main(String[] args) {
        init(); ①

        HttpClient client =
            HttpClient.create()
                .metrics(true, s -> {
                    if (s.startsWith("/stream/")) { ②
                        return "/stream/{n}";
                    }
                    return s;
                }); ③

        client.get()
            .uri("https://httpbin.org/stream/3")
            .responseContent()
            .blockLast();
    }

    /**
     * This setup is based on
     * <a
     href="https://micrometer.io/docs/tracing#_micrometer_tracing_brave_setup">Micrometer Tracing Brave Setup</a>
    */
}
```

```

*/
static void init() {
    SpanHandler spanHandler = ZipkinSpanHandler
        .create(AsyncReporter.create(URLConnectionSender.create
            ("http://localhost:9411/api/v2/spans")));

    StrictCurrentTraceContext braveCurrentTraceContext =
        StrictCurrentTraceContext.create();

    CurrentTraceContext bridgeContext = new BraveCurrentTraceContext
        (braveCurrentTraceContext);

    Tracing tracing =
        Tracing.newBuilder()
            .currentTraceContext(braveCurrentTraceContext)
            .supportsJoin(false)
            .traceId128Bit(true)
            .sampler(Sampler.ALWAYS_SAMPLE)
            .addSpanHandler(spanHandler)
            .localServiceName("reactor-netty-examples")
            .build();

    brave.Tracer braveTracer = tracing.tracer();

    Tracer tracer = new BraveTracer(braveTracer, bridgeContext, new
        BraveBaggageManager());

    Propagator propagator = new BravePropagator(tracing);

    OBSERVATION_REGISTRY.observabilityConfig()
        .observationHandler(new
        ReactorNettyPropagatingSenderTracingObservationHandler(tracer, propagator))
        .observationHandler(new
        ReactorNettyTracingObservationHandler(tracer));
}
}

```

- ① Initializes Brave, Zipkin, and the Observation registry.
- ② Templated URIs are used as an URI tag value when possible.
- ③ Enables the built-in integration with Micrometer.

The result in Zipkin looks like:

## REACTOR-NETTY-EXAMPLES

http get

Span ID: a8faba98b5b4430a Parent ID: 080aaad15713b6f2

### Annotations



SHOW ALL ANNOTATIONS

### Tags

http.status\_code  
200

http.url  
/stream/{n}

net.peer.name  
httpbin.org

net.peer.port  
443

reactor.netty.type  
client

## 6.14. Unix Domain Sockets

The **HTTP** client supports Unix Domain Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

`./../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/http/client/uds/Application.java`

```
import io.netty.channel.unix.DomainSocketAddress;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .remoteAddress(() -> new DomainSocketAddress
("/tmp/test.sock")); ①

        client.get()
            .uri("/")
            .response()
            .block();
    }
}
```

① Specifies `DomainSocketAddress` that will be used

## 6.15. Host Name Resolution

By default, the `HttpClient` uses Netty's domain name lookup mechanism that resolves a domain name asynchronously. This is as an alternative of the JVM's built-in blocking resolver.

When you need to change the default settings, you can configure the `HttpClient` as follows:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/resolver/Application.java
```

```
import reactor.netty.http.client.HttpClient;  
  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        HttpClient client =  
            HttpClient.create()  
                .resolver(spec -> spec.queryTimeout(Duration.ofMillis  
(500))); ①  
  
        String response =  
            client.get()  
                .uri("https://example.com/")  
                .responseContent()  
                .aggregate()  
                .asString()  
                .block();  
  
        System.out.println("Response " + response);  
    }  
}
```

① The timeout of each DNS query performed by this resolver will be 500ms.

The following listing shows the available configurations:

Configuration name	Description
<code>cacheMaxTimeToLive</code>	The max time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is greater than this max time to live, this resolver ignores the time to live from the DNS server and uses this max time to live. Default to <code>Integer.MAX_VALUE</code> .



Configuration name	Description
<code>cacheMinTimeToLive</code>	The min time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is less than this min time to live, this resolver ignores the time to live from the DNS server and uses this min time to live. Default: 0.
<code>cacheNegativeTimeToLive</code>	The time to live of the cache for the failed DNS queries (resolution: seconds). Default: 0.
<code>completeOncePreferredResolved</code>	When this setting is enabled, the resolver notifies as soon as all queries for the preferred address type are complete. When this setting is disabled, the resolver notifies when all possible address types are complete. This configuration is applicable for <code>DnsNameResolver#resolveAll(String)</code> . By default, this setting is enabled.
<code>disableOptionalRecord</code>	Disables the automatic inclusion of an optional record that tries to give a hint to the remote DNS server about how much data the resolver can read per response. By default, this setting is enabled.
<code>disableRecursionDesired</code>	Specifies whether this resolver has to send a DNS query with the recursion desired (RD) flag set. By default, this setting is enabled.
<code>hostsFileEntriesResolver</code>	Sets a custom <code>HostsFileEntriesResolver</code> to be used for hosts file entries. Default: <code>DefaultHostsFileEntriesResolver</code> .
<code>maxPayloadSize</code>	Sets the capacity of the datagram packet buffer (in bytes). Default: 4096.
<code>maxQueriesPerResolve</code>	Sets the maximum allowed number of DNS queries to send when resolving a host name. Default: 16.
<code>ndots</code>	Sets the number of dots that must appear in a name before an initial absolute query is made. Default: -1 (to determine the value from the OS on Unix or use a value of 1 otherwise).
<code>queryTimeout</code>	Sets the timeout of each DNS query performed by this resolver (resolution: milliseconds). Default: 5000.
<code>resolvedAddressTypes</code>	The list of the protocol families of the resolved address.
<code>bindAddressSupplier</code>	The supplier of the local address to bind to.

Configuration name	Description
<code>roundRobinSelection</code>	Enables an <code>AddressResolverGroup</code> of <code>DnsNameResolver</code> that supports random selection of destination addresses if multiple are provided by the nameserver. See <code>RoundRobinDnsAddressResolverGroup</code> . Default: <code>DnsAddressResolverGroup</code>
<code>runOn</code>	Performs the communication with the DNS servers on the given <code>LoopResources</code> . By default, the <code>LoopResources</code> specified on the client level are used.
<code>searchDomains</code>	The list of search domains of the resolver. By default, the effective search domain list is populated by using the system DNS search domains.
<code>trace</code>	A specific logger and log level to be used by this resolver when generating detailed trace information in case of resolution failure.

Sometimes, you may want to switch to the JVM built-in resolver. To do so, you can configure the `HttpClient` as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/resolver/custom/Application.java

```
import io.netty.resolver.DefaultAddressResolverGroup;
import reactor.netty.http.client.HttpClient;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .resolver(DefaultAddressResolverGroup.INSTANCE); ①

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① Sets the JVM built-in resolver.

## 6.16. Timeout Configuration

This section describes various timeout configuration options that can be used in `HttpClient`. Configuring a proper timeout may improve or solve issues in the communication process. The configuration options can be grouped as follows:

- [Connection Pool Timeout](#)
- [HttpClient Timeout](#)
  - [Response Timeout](#)
  - [Connection Timeout](#)
  - [SSL/TLS Timeout](#)
  - [Proxy Timeout](#)
  - [Host Name Resolution Timeout](#)

### 6.16.1. Connection Pool Timeout

By default, `HttpClient` uses a connection pool. When a request is completed successfully and if the

connection is not scheduled for closing, the connection is returned to the connection pool and can thus be reused for processing another request. The connection may be reused immediately for another request or may stay idle in the connection pool for some time.

The following list describes the available timeout configuration options:

- `maxIdleTime` - The maximum time (resolution: ms) that this connection stays idle in the connection pool. By default, `maxIdleTime` is not specified.



When you configure `maxIdleTime`, you should consider the idle timeout configuration on the target server. Choose a configuration that is equal to or less than the one on the target server. By doing so, you can reduce the I/O issues caused by a connection closed by the target server.

- `maxLifeTime` - The maximum time (resolution: ms) that this connection stays alive. By default, `maxLifeTime` is not specified.
- `pendingAcquireTimeout` - The maximum time (resolution: ms) after which a pending acquire operation must complete, or a `PoolAcquireTimeoutException` is thrown. Default: 45s.

By default, these timeouts are checked on connection `release` or `acquire` operations and, if some timeout is reached, the connection is closed and removed from the connection pool. However, you can also configure the connection pool, by setting `evictInBackground`, to perform periodic checks on connections.

To customize the default settings, you can configure `HttpClient` as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/pool/Application.java

```
import reactor.netty.http.client.HttpClient;
import reactor.netty.resources.ConnectionProvider;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        ConnectionProvider provider =
            ConnectionProvider.builder("custom")
                .maxConnections(50)
                .maxIdleTime(Duration.ofSeconds(20))
                .maxLifeTime(Duration.ofSeconds(60))
                .pendingAcquireTimeout(Duration.ofSeconds(60))
                .evictInBackground(Duration.ofSeconds(120))
                .build();

        HttpClient client = HttpClient.create(provider);

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);

        provider.disposeLater()
            .block();
    }
}
```

- ① Configures the maximum time for a connection to stay idle to 20 seconds.
- ② Configures the maximum time for a connection to stay alive to 60 seconds.
- ③ Configures the maximum time for the pending acquire operation to 60 seconds.
- ④ Every two minutes, the connection pool is regularly checked for connections that are applicable for removal.

## 6.16.2. HttpClient Timeout

This section provides information for the various timeout configuration options at the `HttpClient` level.



Reactor Netty uses Reactor Core as its Reactive Streams implementation, and you may want to use the `timeout` operator that `Mono` and `Flux` provide. Keep in mind, however, that it is better to use the more specific timeout configuration options available in Reactor Netty, since they provide more control for a specific purpose and use case. By contrast, the `timeout` operator can only apply to the operation as a whole, from establishing the connection to the remote peer to receiving the response.

### Response Timeout

`HttpClient` provides an API for configuring a default response timeout for all requests. You can change this default response timeout through an API for a specific request. By default, `responseTimeout` is not specified.



It is always a good practice to configure a response timeout.

To customize the default settings, you can configure `HttpClient` as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/read/timeout/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.http.client.HttpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .responseTimeout(Duration.ofSeconds(1));    ①

        String response1 =
            client.post()
                .uri("https://example.com/")
                .send((req, out) -> {
                    req.responseTimeout(Duration.ofSeconds(2));    ②
                    return out.sendString(Mono.just("body1"));
                })
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response1);

        String response2 =
            client.post()
                .uri("https://example.com/")
                .send((req, out) -> out.sendString(Mono.just("body2")))
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response2);
    }
}
```

① Configures the default response timeout to 1 second.

② Configures a response timeout for a specific request to 2 seconds.

## Connection Timeout

The following listing shows all available connection timeout configuration options, but some of them may apply only to a specific transport.

- **CONNECT\_TIMEOUT\_MILLIS** - If the connection establishment attempt to the remote peer does not finish within the configured connect timeout (resolution: ms), the connection establishment attempt fails. Default: 30s.
- **SO\_KEEPALIVE** - When the connection stays idle for some time (the time is implementation dependent, but the default is typically two hours), TCP automatically sends a **keepalive** probe to the remote peer. By default, **SO\_KEEPALIVE** is not enabled. When you run with **Epoll/NIO** (since **Java 11 on Mac or Linux**) transport, you may also configure:
  - **TCP\_KEEPIDLE** - The maximum time (resolution: seconds) that this connection stays idle before TCP starts sending **keepalive** probes, if **SO\_KEEPALIVE** has been set. The maximum time is implementation dependent, but the default is typically two hours.
  - **TCP\_KEEPINTVL** (Epoll)/**TCP\_KEEPINTERVAL** (NIO) - The time (resolution: seconds) between individual **keepalive** probes.
  - **TCP\_KEEPCNT** (Epoll)/**TCP\_KEEPCOUNT** (NIO) - The maximum number of **keepalive** probes TCP should send before dropping the connection.



Sometimes, between the client and the server, you may have a network component that silently drops the idle connections without sending a response. From the Reactor Netty point of view, in this use case, the remote peer just does not respond. To be able to handle such a use case you may consider configuring **SO\_KEEPALIVE**.

To customize the default settings, you can configure **HttpClient** as follows:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/channeloptions/Application  
.java

```
import io.netty.channel.ChannelOption;
import io.netty.channel.epoll.EpollChannelOption;
//import io.netty.channel.socket.nio.NioChannelOption;
//import jdk.net.ExtendedSocketOptions;
import reactor.netty.http.client.HttpClient;
import java.net.InetSocketAddress;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .bindAddress(() -> new InetSocketAddress("host", 1234))
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000) ①
                .option(ChannelOption.SO_KEEPALIVE, true) ②
                // The options below are available only when NIO
transport (Java 11) is used
                // on Mac or Linux (Java does not currently support
these extended options on Windows)
                // https://bugs.openjdk.java.net/browse/JDK-8194298

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPIDLE), 300)

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPINTERVAL), 60)

                // .option(NioChannelOption.of(ExtendedSocketOptions.TCP_KEEPCOUNT), 8);
                // The options below are available only when Epoll
transport is used
                .option(EpollChannelOption.TCP_KEEPIDLE, 300) ③
                .option(EpollChannelOption.TCP_KEEPINTVL, 60) ④
                .option(EpollChannelOption.TCP_KEEPCNT, 8); ⑤

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① Configures the connection establishment timeout to 10 seconds.

- ② Enables TCP `keepalive`. This means that TCP starts sending `keepalive` probes when a connection is idle for some time.
- ③ The connection needs to remain idle for 5 minutes before TCP starts sending `keepalive` probes.
- ④ Configures the time between individual `keepalive` probes to 1 minute.
- ⑤ Configures the maximum number of TCP `keepalive` probes to 8.

## SSL/TLS Timeout

`HttpClient` supports the SSL/TLS functionality provided by Netty.

The following list describes the available timeout configuration options:

- `handshakeTimeout` - Use this option to configure the SSL handshake timeout (resolution: ms). Default: 10s.



You should consider increasing the SSL handshake timeout when expecting slow network connections.

- `closeNotifyFlushTimeout` - Use this option to configure the SSL `close_notify` flush timeout (resolution: ms). Default: 3s.
- `closeNotifyReadTimeout` - Use this option to configure the SSL `close_notify` read timeout (resolution: ms). Default: 0s.

To customize the default settings, you can configure `HttpClient` as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/http/client/security/custom/Application.  
n.java

```
import reactor.netty.http.Http11SslContextSpec;
import reactor.netty.http.client.HttpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Http11SslContextSpec http11SslContextSpec = Http11SslContextSpec.
forClient();

        HttpClient client =
            HttpClient.create()
                .secure(spec -> spec.sslContext(http11SslContextSpec)
                    .handshakeTimeout(Duration.
ofSeconds(30))          ①
                    .closeNotifyFlushTimeout(Duration
.ofSeconds(10))        ②
                    .closeNotifyReadTimeout(Duration
.ofSeconds(10)));      ③

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

- ① Configures the SSL handshake timeout to 30 seconds.
- ② Configures the SSL `close_notify` flush timeout to 10 seconds.
- ③ Configures the SSL `close_notify` read timeout to 10 seconds.

## Proxy Timeout

`HttpClient` supports the proxy functionality provided by Netty and provides a way to specify the `connection establishment timeout`. If the connection establishment attempt to the remote peer does not finish within the timeout, the connection establishment attempt fails. Default: 10s.

To customize the default settings, you can configure `HttpClient` as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/http/client/proxy/Application.java

```
import reactor.netty.http.client.HttpClient;
import reactor.netty.transport.ProxyProvider;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .proxy(spec -> spec.type(ProxyProvider.Proxy.HTTP)
                    .host("proxy")
                    .port(8080)
                    .nonProxyHosts("localhost")
                    .connectTimeoutMillis(20_000)); ①

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① Configures the connection establishment timeout to 20 seconds.

## Host Name Resolution Timeout

By default, the `HttpClient` uses Netty's domain name lookup mechanism to resolve a domain name asynchronously.

The following list describes the available timeout configuration options:

- `cacheMaxTimeToLive` - The maximum time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is greater than this maximum time to live, this resolver ignores the time to live from the DNS server and uses this maximum time to live. Default: `Integer.MAX_VALUE`.
- `cacheMinTimeToLive` - The minimum time to live of the cached DNS resource records (resolution: seconds). If the time to live of the DNS resource record returned by the DNS server is less than this minimum time to live, this resolver ignores the time to live from the DNS server and uses this minimum time to live. Default: 0s.
- `cacheNegativeTimeToLive` - The time to live of the cache for the failed DNS queries (resolution: seconds). Default: 0s.

- `queryTimeout` - Sets the timeout of each DNS query performed by this resolver (resolution: milliseconds). Default: 5s.

To customize the default settings, you can configure `HttpClient` as follows:

`../../reactor-netty-`

`examples/src/main/java/reactor/netty/examples/documentation/http/client/resolver/Application.java`

```
import reactor.netty.http.client.HttpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        HttpClient client =
            HttpClient.create()
                .resolver(spec -> spec.queryTimeout(Duration.ofMillis
(500))); ①

        String response =
            client.get()
                .uri("https://example.com/")
                .responseContent()
                .aggregate()
                .asString()
                .block();

        System.out.println("Response " + response);
    }
}
```

① The timeout of each DNS query performed by this resolver will be 500ms.

# Chapter 7. UDP Server

Reactor Netty provides the easy-to-use and easy-to-configure `UdpServer`. It hides most of the Netty functionality that is required to create a UDP server and adds `Reactive Streams` backpressure.

## 7.1. Starting and Stopping

To start a UDP server, a `UdpServer` instance has to be created and configured. By default, the host is configured to be `localhost` and the port is `12012`. The following example shows how to create and start a UDP server:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/create/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.udp.UdpServer;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection server =  
            UdpServer.create()           ①  
                .bindNow(Duration.ofSeconds(30)); ②  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Creates a `UdpServer` instance that is ready for configuring.

② Starts the server in a blocking fashion and waits for it to finish initializing.

The returned `Connection` offers a simple server API, including `disposeNow()`, which shuts the server down in a blocking fashion.

### 7.1.1. Host and Port

In order to serve on a specific host and port, you can apply the following configuration to the `UDP` server:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/address/Application.java

```
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .host("localhost") ①
                .port(8080)         ②
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Configures the **UDP** server host

② Configures the **UDP** server port

## 7.2. Eager Initialization

By default, the initialization of the **UdpServer** resources happens on demand. This means that the **bind operation** absorbs the extra time needed to initialize and load:

- the event loop group
- the native transport libraries (when native transport is used)

When you need to preload these resources, you can configure the **UdpServer** as follows:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/udp/server/warmup/Application.java

```
import io.netty.channel.socket.DatagramPacket;
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        UdpServer udpServer =
            UdpServer.create()
                .handle((in, out) ->
                    out.sendObject(
                        in.receiveObject()
                            .map(o -> {
                                if (o instanceof DatagramPacket) {
                                    DatagramPacket p = (DatagramPacket) o;
                                    return new DatagramPacket(p.content
                                        ().retain(), p.sender());
                                }
                                else {
                                    return Mono.error(new Exception
                                        ("Unexpected type of the message: " + o));
                                }
                            }
                        )));

        udpServer.warmup() ①
            .block();

        Connection server = udpServer.bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Initialize and load the event loop group and the native transport libraries

## 7.3. Writing Data

To send data to the remote peer, you must attach an I/O handler. The I/O handler has access to `UdpOutbound`, to be able to write data. The following example shows how to send `hello`:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/send/Application.java

```
import io.netty.buffer.ByteBuf;
import io.netty.buffer.Unpooled;
import io.netty.channel.socket.DatagramPacket;
import io.netty.util.CharsetUtil;
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .handle((in, out) ->
                    out.sendObject(
                        in.receiveObject()
                            .map(o -> {
                                if (o instanceof DatagramPacket) {
                                    DatagramPacket p = (DatagramPacket) o;
                                    ByteBuf buf = Unpooled.copiedBuffer
("hello", CharsetUtil.UTF_8);

                                    return new DatagramPacket(buf, p.
sender()); ①
                                }
                                else {
                                    return Mono.error(new Exception
("Unexpected type of the message: " + o));
                                }
                            })))
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Sends a `hello` string to the remote peer

## 7.4. Consuming Data

To receive data from a remote peer, you must attach an I/O handler. The I/O handler has access to `UdpInbound`, to be able to read data. The following example shows how to consume data:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/read/Application.java

```
import io.netty.channel.socket.DatagramPacket;
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .handle((in, out) ->
                    out.sendObject(
                        in.receiveObject()
                            .map(o -> {
                                if (o instanceof DatagramPacket) {
                                    DatagramPacket p = (DatagramPacket) o;
                                    return new DatagramPacket(p.content
                                        ().retain(), p.sender()); ①
                                }
                                else {
                                    return Mono.error(new Exception
                                        ("Unexpected type of the message: " + o));
                                }
                            })))
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Receives data from the remote peer

## 7.5. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `UdpServer`:

Callback	Description
<code>doOnBind</code>	Invoked when the server channel is about to bind.
<code>doOnBound</code>	Invoked when the server channel is bound.
<code>doOnChannelInit</code>	Invoked when initializing the channel.

Callback	Description
<code>doOnUnbound</code>	Invoked when the server channel is unbound.

The following example uses the `doOnBound` and `doOnChannelInit` callbacks:

`./../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/udp/server/lifecycle/Application.java`

```
import io.netty.handler.codec.LineBasedFrameDecoder;
import io.netty.handler.logging.LoggingHandler;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .doOnBound(conn -> conn.addHandlerLast(new
LineBasedFrameDecoder(8192))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))) ②
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Netty pipeline is extended with `LineBasedFrameDecoder` when the server channel is bound.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 7.6. Connection Configuration

This section describes three kinds of configuration that you can use at the UDP level:

- [Channel Options](#)
- [Wire Logger](#)
- [Event Loop Group](#)

### 7.6.1. Channel Options

By default, the `UDP` server is configured with the following options:

*../../reactor-netty-core/src/main/java/reactor/netty/udp/UdpServerBind.java*

```
UdpServerBind() {
    this.config = new UdpServerConfig(
        Collections.singletonMap(ChannelOption.AUTO_READ, false),
        () -> new InetSocketAddress(NetUtil.LOCALHOST, DEFAULT_PORT));
}
```

If you need additional options or need to change the current options, you can apply the following configuration:

*../../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/udp/server/channeloptions/Application.java*

```
import io.netty.channel.ChannelOption;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000)
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

For more information about Netty channel options, see the following links:

- [Common ChannelOption](#)
- [Epoll ChannelOption](#)
- [KQueue ChannelOption](#)
- [Socket Options](#)

### 7.6.2. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected. By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.udp.UdpServer` level to `DEBUG` and apply the following configuration:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/wiretap/Application.java

```
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .wiretap(true) ①
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Enables the wire logging

## Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/wiretap/custom/Application.java

```
import io.netty.handler.logging.LogLevel;
import reactor.netty.Connection;
import reactor.netty.transport.logging.AdvancedByteBufFormat;
import reactor.netty.udp.UdpServer;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .wiretap("logger-name", LogLevel.DEBUG,
AdvancedByteBufFormat.TEXTUAL) ①
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

### 7.6.3. Event Loop Group

By default, the UDP server uses “Event Loop Group,” where the number of the worker threads equals the number of processors available to the runtime on initialization (but with a minimum value of 4). When you need a different configuration, you can use one of the [LoopResource#create](#) methods.

The default configuration for the “Event Loop Group” is the following:



*./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java*

```
/**
 * Default worker thread count, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String IO_WORKER_COUNT = "reactor.netty.ioWorkerCount";
/**
 * Default selector thread count, fallback to -1 (no selector thread)
 */
public static final String IO_SELECT_COUNT = "reactor.netty.ioSelectCount";
/**
 * Default worker thread count for UDP, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String UDP_IO_THREAD_COUNT =
"reactor.netty.udp.ioThreadCount";
/**
 * Default quiet period that guarantees that the disposal of the underlying
 LoopResources
 * will not happen, fallback to 2 seconds.
 */
public static final String SHUTDOWN_QUIET_PERIOD =
"reactor.netty.ioShutdownQuietPeriod";
/**
 * Default maximum amount of time to wait until the disposal of the underlying
 LoopResources
 * regardless if a task was submitted during the quiet period, fallback to 15
 seconds.
 */
public static final String SHUTDOWN_TIMEOUT = "reactor.netty.ioShutdownTimeout";
/**
 * Default value whether the native transport (epoll, kqueue) will be preferred,
 * fallback it will be preferred when available
 */
public static final String NATIVE = "reactor.netty.native";
```

If you need changes to these settings, you can apply the following configuration:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/eventloop/Application.java

```
import reactor.netty.Connection;
import reactor.netty.resources.LoopResources;
import reactor.netty.udp.UdpServer;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        LoopResources loop = LoopResources.create("event-loop", 1, 4, true);

        Connection server =
            UdpServer.create()
                .runOn(loop)
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

## 7.7. Metrics

The UDP server supports built-in integration with `Micrometer`. It exposes all metrics with a prefix of `reactor.netty.udp.server`.

The following table provides information for the UDP server metrics:

metric name	type	description
reactor.netty.udp.server.data.received	DistributionSummary	Amount of the data received, in bytes. See <a href="#">Data Received</a>
reactor.netty.udp.server.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.udp.server.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>

These additional metrics are also available:

`ByteBufAllocator` metrics

metric name	type	description
reactor.netty.bytebuf allocator. used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf allocator. used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>
reactor.netty.bytebuf allocator. heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf allocator. direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>
reactor.netty.bytebuf allocator. threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf allocator. small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>
reactor.netty.bytebuf allocator. normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf allocator. chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>
reactor.netty.bytebuf allocator. active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf allocator. active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending .tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/metrics/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.udp.UdpServer;  
  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection server =  
            UdpServer.create()  
                .metrics(true) ①  
                .bindNow(Duration.ofSeconds(30));  
  
        server.onDispose()  
            .block();  
    }  
}
```

① Enables the built-in integration with Micrometer

When UDP server metrics are needed for an integration with a system other than **Micrometer** or you want to provide your own integration with **Micrometer**, you can provide your own metrics recorder, as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/server/metrics/custom/Application.java

```
import reactor.netty.Connection;
import reactor.netty.channel.ChannelMetricsRecorder;
import reactor.netty.udp.UdpServer;

import java.net.SocketAddress;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .metrics(true, CustomChannelMetricsRecorder::new) ①
                .bindNow(Duration.ofSeconds(30));

        server.onDispose()
            .block();
    }
}
```

① Enables UDP server metrics and provides `ChannelMetricsRecorder` implementation.

## 7.8. Unix Domain Sockets

The `UdpServer` supports Unix Domain Datagram Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

../../reactor-netty-

examples/src/main/java/reactor/netty/examples/documentation/udp/server/uds/Application.java

```
import io.netty.channel.unix.DomainDatagramPacket;
import io.netty.channel.unix.DomainSocketAddress;
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpServer;

import java.io.File;

public class Application {

    public static void main(String[] args) {
        Connection server =
            UdpServer.create()
                .bindAddress(Application::newDomainSocketAddress) ①
                .handle((in, out) ->
                    out.sendObject(
                        in.receiveObject()
                            .map(o -> {
                                if (o instanceof DomainDatagramPacket) {
                                    DomainDatagramPacket p =
                                        (DomainDatagramPacket) o;
                                    return new DomainDatagramPacket(p
                                        .content().retain(), p.sender());
                                }
                                else {
                                    return Mono.error(new Exception
                                        ("Unexpected type of the message: " + o));
                                }
                            })))
                .bindNow();

        server.onDispose()
            .block();
    }
}
```

① Specifies `DomainSocketAddress` that will be used

# Chapter 8. UDP Client

Reactor Netty provides the easy-to-use and easy-to-configure `UdpClient`. It hides most of the Netty functionality that is required to create a UDP client and adds Reactive Streams backpressure.

## 8.1. Connecting and Disconnecting

To connect the UDP client to a given endpoint, you must create and configure a `UdpClient` instance. By default, the host is configured for `localhost` and the port is `12012`. The following example shows how to create and connect a UDP client:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/create/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.udp.UdpClient;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            UdpClient.create() ①  
                .connectNow(Duration.ofSeconds(30)); ②  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Creates a `UdpClient` instance that is ready for configuring.

② Connects the client in a blocking fashion and waits for it to finish initializing.

The returned `Connection` offers a simple connection API, including `disposeNow()`, which shuts the client down in a blocking fashion.

### 8.1.1. Host and Port

To connect to a specific `host` and `port`, you can apply the following configuration to the `UDP` client:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/address/Application.java

```
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com") ①
                .port(80)             ②
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Configures the **host** to which this client should connect

② Configures the **port** to which this client should connect

## 8.2. Eager Initialization

By default, the initialization of the **UdpClient** resources happens on demand. This means that the **connect operation** absorbs the extra time needed to initialize and load:

- the event loop group
- the host name resolver
- the native transport libraries (when native transport is used)

When you need to preload these resources, you can configure the **UdpClient** as follows:



../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/warmup/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        UdpClient udpClient = UdpClient.create()
            .host("example.com")
            .port(80)
            .handle((udpInbound, udpOutbound) ->
udpOutbound.sendString(Mono.just("hello")));

        udpClient.warmup() ①
            .block();

        Connection connection = udpClient.connectNow(Duration.ofSeconds(30)); ②

        connection.onDispose()
            .block();
    }
}
```

- ① Initialize and load the event loop group, the host name resolver, and the native transport libraries
- ② Host name resolution happens when connecting to the remote peer

## 8.3. Writing Data

To send data to a given peer, you must attach an I/O handler. The I/O handler has access to `UdpOutbound`, to be able to write data.

The following example shows how to send `hello`:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/send/Application.java

```
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .handle((udpInbound, udpOutbound) -> udpOutbound
                    .sendString(Mono.just("hello"))) ①
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Sends `hello` string to the remote peer.

## 8.4. Consuming Data

To receive data from a given peer, you must attach an I/O handler. The I/O handler has access to `UdpInbound`, to be able to read data. The following example shows how to consume data:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/read/Application.java

```
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .handle((udpInbound, udpOutbound) -> udpInbound.
receive().then()) ①
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Receives data from a given peer

## 8.5. Lifecycle Callbacks

The following lifecycle callbacks are provided to let you extend the `UdpClient`:

Callback	Description
<code>doAfterResolve</code>	Invoked after the remote address has been resolved successfully.
<code>doOnChannelInit</code>	Invoked when initializing the channel.
<code>doOnConnect</code>	Invoked when the channel is about to connect.
<code>doOnConnected</code>	Invoked after the channel has been connected.
<code>doOnDisconnected</code>	Invoked after the channel has been disconnected.
<code>doOnResolve</code>	Invoked when the remote address is about to be resolved.
<code>doOnResolveError</code>	Invoked in case the remote address hasn't been resolved successfully.

The following example uses the `doOnConnected` and `doOnChannelInit` callbacks:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/lifecycle/Application.java

```
import io.netty.handler.codec.LineBasedFrameDecoder;
import io.netty.handler.logging.LoggingHandler;
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .doOnConnected(conn -> conn.addHandlerLast(new
LineBasedFrameDecoder(8192))) ①
                .doOnChannelInit((observer, channel, remoteAddress) ->
                    channel.pipeline()
                        .addFirst(new LoggingHandler
("reactor.netty.examples"))) ②
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Netty pipeline is extended with `LineBasedFrameDecoder` when the channel has been connected.

② Netty pipeline is extended with `LoggingHandler` when initializing the channel.

## 8.6. Connection Configuration

This section describes three kinds of configuration that you can use at the UDP level:

- [Channel Options](#)
- [Wire Logger](#)
- [Event Loop Group](#)

### 8.6.1. Channel Options

By default, the `UDP` client is configured with the following options:

*../../reactor-netty-core/src/main/java/reactor/netty/udp/UdpClientConnect.java*

```
UdpClientConnect() {
    this.config = new UdpClientConfig(
        ConnectionProvider.newConnection(),
        Collections.singletonMap(ChannelOption.AUTO_READ, false),
        () -> new InetSocketAddress(NetUtil.LOCALHOST, DEFAULT_PORT));
}
```

If you need additional options or need to change the current options, you can apply the following configuration:

*../../reactor-netty-examples/src/main/java/reactor/netty/examples/documentation/udp/client/channeloptions/Application.java*

```
import io.netty.channel.ChannelOption;
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .option(ChannelOption.CONNECT_TIMEOUT_MILLIS, 10000)
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

You can find more about Netty channel options at the following links:

- [Common ChannelOption](#)
- [Epoll ChannelOption](#)
- [KQueue ChannelOption](#)
- [Socket Options](#)

## 8.6.2. Wire Logger

Reactor Netty provides wire logging for when the traffic between the peers needs to be inspected. By default, wire logging is disabled. To enable it, you must set the logger `reactor.netty.udp.UdpClient` level to `DEBUG` and apply the following configuration:

```
./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/wiretap/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.udp.UdpClient;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            UdpClient.create()  
                .host("example.com")  
                .port(80)  
                .wiretap(true) ①  
                .connectNow(Duration.ofSeconds(30));  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging

### Wire Logger formatters

Reactor Netty supports 3 different formatters:

- [AdvancedByteBufferFormat#HEX\\_DUMP](#) - the default

```
/**
 * When wire logging is enabled with this format, both events and content will be
 * logged.
 * The content will be in hex format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] REGISTERED
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] ACTIVE
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] READ: 145B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 50 4f 53 54 20 2f 74 65 73 74 2f 57 6f 72 6c 64 |POST /test/World|
 * |00000010| 20 48 54 54 50 2f 31 2e 31 0d 0a 43 6f 6e 74 65 | HTTP/1.1..Conte|
 * |00000020| 6e 74 2d 54 79 70 65 3a 20 74 65 78 74 2f 70 6c |nt-Type: text/pl|
 * |00000030| 61 69 6e 0d 0a 75 73 65 72 2d 61 67 65 6e 74 3a |ain..user-agent:|
 * |00000040| 20 52 65 61 63 74 6f 72 4e 65 74 74 79 2f 64 65 | ReactorNetty/de|
 * ...
 * reactor.netty.http.HttpTests - [d5230a14, L:/0:0:0:0:0:0:1:60267 -
R:/0:0:0:0:0:0:1:60269] WRITE: 38B
 *
 *      +-----+
 *      | 0 1 2 3 4 5 6 7 8 9 a b c d e f |
 * +-----+-----+-----+-----+-----+
 * |00000000| 48 54 54 50 2f 31 2e 31 20 32 30 30 20 4f 4b 0d |HTTP/1.1 200 OK.|
 * |00000010| 0a 63 6f 6e 74 65 6e 74 2d 6c 65 6e 67 74 68 3a |.content-length:|
 * |00000020| 20 30 0d 0a 0d 0a                                | 0....          |
 * +-----+-----+-----+-----+-----+
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#SIMPLE](#)

`./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java`

```
/**
 * When wire logging is enabled with this format, only the events will be logged.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] REGISTERED
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] ACTIVE
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] READ: 145B
 * reactor.netty.http.HttpTests - [230d3686, L:/0:0:0:0:0:0:1:60241 -
R:/0:0:0:0:0:0:1:60245] WRITE: 38B
 * }
 * </pre>
 */
```

- [AdvancedByteBufFormat#TEXTUAL](#)

`./../reactor-netty-core/src/main/java/reactor/netty/transport/logging/AdvancedByteBufFormat.java`

```
/**
 * When wire logging is enabled with this format, both events and content will be
logged.
 * The content will be in plain text format.
 * <p>Examples:</p>
 * <pre>
 * {@code
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] REGISTERED
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] ACTIVE
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] READ: 145B POST /test/World HTTP/1.1
 * Content-Type: text/plain
 * user-agent: ReactorNetty/dev
 * ...
 * reactor.netty.http.HttpTests - [02c3db6c, L:/0:0:0:0:0:0:1:60317 -
R:/0:0:0:0:0:0:1:60319] WRITE: 38B HTTP/1.1 200 OK
 * content-length: 0
 * }
 * </pre>
 */
```

When you need to change the default formatter you can configure it as follows:



```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/wiretap/custom/Application  
.java
```

```
import io.netty.handler.logging.LogLevel;  
import reactor.netty.Connection;  
import reactor.netty.transport.logging.AdvancedByteBufFormat;  
import reactor.netty.udp.UdpClient;  
  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        Connection connection =  
            UdpClient.create()  
                .host("example.com")  
                .port(80)  
                .wiretap("logger-name", LogLevel.DEBUG,  
AdvancedByteBufFormat.TEXTUAL) ①  
                .connectNow(Duration.ofSeconds(30));  
  
        connection.onDispose()  
            .block();  
    }  
}
```

① Enables the wire logging, [AdvancedByteBufFormat#TEXTUAL](#) is used for printing the content.

### 8.6.3. Event Loop Group

By default, the UDP client uses “Event Loop Group,” where the number of the worker threads equals the number of processors available to the runtime on initialization (but with a minimum value of 4). When you need a different configuration, you can use one of the [LoopResources#create](#) methods.

The following listing shows the default configuration for the “Event Loop Group”:

*./../reactor-netty-core/src/main/java/reactor/netty/ReactorNetty.java*

```
/**
 * Default worker thread count, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String IO_WORKER_COUNT = "reactor.netty.ioWorkerCount";
/**
 * Default selector thread count, fallback to -1 (no selector thread)
 */
public static final String IO_SELECT_COUNT = "reactor.netty.ioSelectCount";
/**
 * Default worker thread count for UDP, fallback to available processor
 * (but with a minimum value of 4)
 */
public static final String UDP_IO_THREAD_COUNT =
"reactor.netty.udp.ioThreadCount";
/**
 * Default quiet period that guarantees that the disposal of the underlying
LoopResources
 * will not happen, fallback to 2 seconds.
 */
public static final String SHUTDOWN_QUIET_PERIOD =
"reactor.netty.ioShutdownQuietPeriod";
/**
 * Default maximum amount of time to wait until the disposal of the underlying
LoopResources
 * regardless if a task was submitted during the quiet period, fallback to 15
seconds.
 */
public static final String SHUTDOWN_TIMEOUT = "reactor.netty.ioShutdownTimeout";
/**
 * Default value whether the native transport (epoll, kqueue) will be preferred,
 * fallback it will be preferred when available
 */
public static final String NATIVE = "reactor.netty.native";
```

If you need changes to the these settings, you can apply the following configuration:

```
../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/eventloop/Application.java
```

```
import reactor.netty.Connection;  
import reactor.netty.resources.LoopResources;  
import reactor.netty.udp.UdpClient;  
import java.time.Duration;  
  
public class Application {  
  
    public static void main(String[] args) {  
        LoopResources loop = LoopResources.create("event-loop", 1, 4, true);  
  
        Connection connection =  
            UdpClient.create()  
                .host("example.com")  
                .port(80)  
                .runOn(loop)  
                .connectNow(Duration.ofSeconds(30));  
  
        connection.onDispose()  
            .block();  
    }  
}
```

## 8.7. Metrics

The UDP client supports built-in integration with [Micrometer](#). It exposes all metrics with a prefix of `reactor.netty.udp.client`.

The following table provides information for the UDP client metrics:

metric name	type	description
reactor.netty.udp.client.data.received	DistributionSummary	Amount of the data received, in bytes. See <a href="#">Data Received</a>
reactor.netty.udp.client.data.sent	DistributionSummary	Amount of the data sent, in bytes. See <a href="#">Data Sent</a>
reactor.netty.udp.client.errors	Counter	Number of errors that occurred. See <a href="#">Errors Count</a>
reactor.netty.udp.client.connect.time	Timer	Time spent for connecting to the remote address. See <a href="#">Connect Time</a>
reactor.netty.udp.client.address.resolver	Timer	Time spent for resolving the address. See <a href="#">Hostname Resolution Time</a>

These additional metrics are also available:

#### ByteBufAllocator metrics

metric name	type	description
reactor.netty.bytebuf.allocator.used.heap.memory	Gauge	The number of bytes reserved by heap buffer allocator. See <a href="#">Used Heap Memory</a>
reactor.netty.bytebuf.allocator.used.direct.memory	Gauge	The number of bytes reserved by direct buffer allocator. See <a href="#">Used Direct Memory</a>
reactor.netty.bytebuf.allocator.heap.arenas	Gauge	The number of heap arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Heap Arenas</a>
reactor.netty.bytebuf.allocator.direct.arenas	Gauge	The number of direct arenas (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Direct Arenas</a>
reactor.netty.bytebuf.allocator.threadlocal.caches	Gauge	The number of thread local caches (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Thread Local Caches</a>
reactor.netty.bytebuf.allocator.small.cache.size	Gauge	The size of the small cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Small Cache Size</a>
reactor.netty.bytebuf.allocator.normal.cache.size	Gauge	The size of the normal cache (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Normal Cache Size</a>
reactor.netty.bytebuf.allocator.chunk.size	Gauge	The chunk size for an arena (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Chunk Size</a>
reactor.netty.bytebuf.allocator.active.heap.memory	Gauge	The actual bytes consumed by in-use buffers allocated from heap buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Heap Memory</a>
reactor.netty.bytebuf.allocator.active.direct.memory	Gauge	The actual bytes consumed by in-use buffers allocated from direct buffer pools (when <a href="#">PooledByteBufAllocator</a> ). See <a href="#">Active Direct Memory</a>

#### EventLoop metrics

metric name	type	description
reactor.netty.eventloop.pending tasks	Gauge	The number of tasks that are pending for processing on an event loop. See <a href="#">Pending Tasks</a>

The following example enables that integration:

*./../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/metrics/Application.java*

```
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;

import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .metrics(true) ①
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Enables the built-in integration with Micrometer

When UDP client metrics are needed for an integration with a system other than **Micrometer** or you want to provide your own integration with **Micrometer**, you can provide your own metrics recorder, as follows:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/metrics/custom/Application.  
java

```
import reactor.netty.Connection;
import reactor.netty.channel.ChannelMetricsRecorder;
import reactor.netty.udp.UdpClient;

import java.net.SocketAddress;
import java.time.Duration;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .host("example.com")
                .port(80)
                .metrics(true, CustomChannelMetricsRecorder::new) ①
                .connectNow(Duration.ofSeconds(30));

        connection.onDispose()
            .block();
    }
}
```

① Enables UDP client metrics and provides `ChannelMetricsRecorder` implementation.

## 8.8. Unix Domain Sockets

The `UdpClient` supports Unix Domain Datagram Sockets (UDS) when native transport is in use.

The following example shows how to use UDS support:

../../reactor-netty-  
examples/src/main/java/reactor/netty/examples/documentation/udp/client/uds/Application.java

```
import io.netty.channel.unix.DomainSocketAddress;
import reactor.core.publisher.Mono;
import reactor.netty.Connection;
import reactor.netty.udp.UdpClient;

import java.io.File;

public class Application {

    public static void main(String[] args) {
        Connection connection =
            UdpClient.create()
                .bindAddress(Application::newDomainSocketAddress)
                .remoteAddress(() -> new DomainSocketAddress("/tmp/test-
server.sock")) ①
                .handle((in, out) ->
                    out.sendString(Mono.just("hello"))
                        .then(in.receive()
                            .asString()
                            .doOnNext(System.out::println)
                            .then()))
                .connectNow();

        connection.onDispose()
            .block();
    }
}
```

① Specifies `DomainSocketAddress` that will be used

# Appendix A: Frequently Asked Questions

This section covers the following content:

- [Connection to the proxy cannot be established](#)
- [What is it meaning of the information that is prepended to every log record?](#)
- [How can I extract all log records for a particular HTTP request?](#)
- [How can I debug a memory leak?](#)
- [How can I debug "Connection prematurely closed BEFORE response"?](#)

## A.1. Connection to the proxy cannot be established

Netty's HTTP proxy support always uses `CONNECT` method in order to establish a tunnel to the specified proxy regardless of the scheme that is used `http` or `https`. (More information: [Netty enforce HTTP proxy to support HTTP CONNECT method](#)). Some proxies might not support `CONNECT` method when the scheme is `http` or might need to be configured in order to support this way of communication. Sometimes this might be the reason for not being able to connect to the proxy. Consider checking the proxy documentation whether it supports or needs an additional configuration in order to support `CONNECT` method.

## A.2. What is it meaning of the information that is prepended to every log record?

Reactor Netty adds information for the connection at the beginning of every log record (when this is possible). There is a slight difference in the details for the connection when you use `TCP`, `UDP`, `HTTP/1.1` or `HTTP/2`.

### A.2.1. TCP and UDP

In case of `TCP` and `UDP`, the following is added at the beginning of every log record: the id of the underlying connection, local and remote addresses.

#### Examples

```
[a1566d55, L:/[0:0:0:0:0:0:1]:53446 - R:/[0:0:0:0:0:0:1]:53444]
```

```
[a1566d55, L:/[0:0:0:0:0:0:1]:53446 ! R:/[0:0:0:0:0:0:1]:53444]
```

#### Format

```
[<CONNECTION_ID>, L:<LOCAL_ADDRESS> <CONNECTION_OPENED_CLOSED> R:<REMOTE_ADDRESS>]
```

```
<CONNECTION_ID>: a1566d55
```

```
<LOCAL_ADDRESS>: [0:0:0:0:0:0:1]:53446
```

```
<CONNECTION_OPENED_CLOSED>: - (connection opened)
```

```
! (connection closed)
```

```
<REMOTE_ADDRESS>: [0:0:0:0:0:0:1]:53444
```



### A.2.2. HTTP/1.1

In case of **HTTP/1.1**, the following is added at the beginning of every log record: the id of the underlying connection, the serial number of the request received on that connection, local and remote addresses.

#### Examples

```
[a1566d55-5, L:[0:0:0:0:0:0:1]:53446 - R:[0:0:0:0:0:0:1]:53444]
[a1566d55-5, L:[0:0:0:0:0:0:1]:53446 ! R:[0:0:0:0:0:0:1]:53444]
```

#### Format

```
[<CONNECTION_ID>-<REQUEST_NUMBER>, L:<LOCAL_ADDRESS> <CONNECTION_OPENED_CLOSED>
R:<REMOTE_ADDRESS>]
<CONNECTION_ID>: a1566d55
<REQUEST_NUMBER>: 5
<LOCAL_ADDRESS>: [0:0:0:0:0:0:1]:53446
<CONNECTION_OPENED_CLOSED>: - (connection opened)
                             ! (connection closed)
<REMOTE_ADDRESS>: [0:0:0:0:0:0:1]:53444
```

### A.2.3. HTTP/2

In case of **HTTP/2**, the following is added at the beginning of every log record: the id of the underlying connection, local and remote addresses, the id of the stream received on that connection.

#### Examples

```
[a1566d55, L:[0:0:0:0:0:0:1]:53446 - R:[0:0:0:0:0:0:1]:53444](H2 - 5)
[a1566d55, L:[0:0:0:0:0:0:1]:53446 ! R:[0:0:0:0:0:0:1]:53444](H2 - 5)
```

#### Format

```
[<CONNECTION_ID>, L:<LOCAL_ADDRESS> <CONNECTION_OPENED_CLOSED>
R:<REMOTE_ADDRESS><STREAM_ID>]
<CONNECTION_ID>: a1566d55
<LOCAL_ADDRESS>: [0:0:0:0:0:0:1]:53446
<CONNECTION_OPENED_CLOSED>: - (connection opened)
                             ! (connection closed)
<REMOTE_ADDRESS>: [0:0:0:0:0:0:1]:53444
<STREAM_ID>: (H2 - 5)
```

## A.3. How can I extract all log records for a particular HTTP request?

Reactor Netty adds information for the connection at the beginning of every log record (when this is possible). Use the id of the connection in order to extract all log records for a particular HTTP request. For more information see [What is it meaning of the information that is prepended to every log record?](#)

## A.4. How can I debug a memory leak?

By default, Reactor Netty uses direct memory as this is more performant when there are many native I/O operations (working with sockets), as this can remove the copying operations. As allocation and deallocation are expensive operations, Reactor Netty also uses pooled buffers by default. For more information, see [Reference Counted Objects](#).

To be able to debug memory issues with the direct memory and the pooled buffers, Netty provides a special memory leak detection mechanism. Follow the instructions for [Troubleshooting Buffer Leaks](#) to enable this mechanism. In addition to the instructions provided by Netty, Reactor Netty provides a special logger (`_reactor.netty.channel.LeakDetection`) that helps to identify where the memory leak might be located inside Reactor Netty or whether Reactor Netty already forwarded the ownership of the buffers to the application/framework. By default, this logger is disabled. To enable it, increase the log level to `DEBUG`.

Another way to detect memory leaks is to monitor and `reactor.netty.bytebuf allocator.active.heap.memory` and `reactor.netty.bytebuf allocator.active.direct.memory` meters:

- The `reactor.netty.bytebuf allocator.active.heap.memory` provides the actual bytes consumed by in-use buffers allocated from heap buffer pools
- The `reactor.netty.bytebuf allocator.active.direct.memory` provides the actual bytes consumed by in-use buffers allocated from direct buffer pools

If the above meters are constantly growing, then it's likely that there is a buffer memory leak.



Consider reducing the used memory when debugging memory leak issues (e.g. `-XX:MaxDirectMemorySize`, `-Xms`, `-Xmx`). The less memory the application has, the sooner the memory leak will happen.

## A.5. How can I debug "Connection prematurely closed BEFORE response"?

By default, Reactor Netty clients use connection pooling. When a connection is acquired from the connection pool, it is checked to see whether it is still open. However, the connection can be closed at any time after the acquisition. There are many reasons that can cause a connection to be closed. In most cases, the client might not send directly to the server. Instead, there might be other network components (proxies, load balancers, and so on) between them.

If, on the client side, you observe **Connection prematurely closed BEFORE response**, perform the following checks to identify the reason for the connection being closed:

- Obtain a **TCP dump** and check which peer sends a FIN/RST signal.
- Check your network connection.
- Check your Firewall and VPN.
- Check for any proxies and load balancers.
  - Do they have some kind of idle timeout configuration (the connection is closed when there is no incoming data for a certain period of time)?
  - Do they silently drop the idle connections without sending any signal? In order to verify whether this might be the issue, you can enable the TCP keep-alive as described in the section **Connection Timeout**. Issues related to TCP keep-alive configuration on various load balancers were reported in the past.
    - <https://github.com/reactor/reactor-netty/issues/764#issuecomment-1011373248>
    - <https://github.com/reactor/reactor-netty/issues/1510>
    - <https://github.com/reactor/reactor-netty/issues/1843>
- Check the target server. Are there configurations related to any of the following?
  - idle timeout (the connection is closed when there is no incoming data for a certain period of time)
  - limit for buffering data in memory
  - multipart exceeds the max file size limit
  - bad request
  - max keep alive requests (the connection is closed when the requests reach the configured maximum number)

Consider checking **Timeout Configuration**. The section describes various timeout configuration options that are available for Reactor Netty clients. Configuring a proper timeout may improve or solve issues in the communication process.

# Appendix B: Observability

## B.1. Observability metadata

### B.1.1. Observability - Metrics

Below you can find a list of all metrics declared by this project.

#### Active Connections

The number of the connections in the connection pool that have been successfully acquired and are in active use.

**Metric name** `reactor.netty.connection.provider.active.connections`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.client.Http2ConnectionProviderMeters`.

Table 1. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>name</code> (required)	NAME.
<code>remote.address</code> (required)	Remote address.

#### Active Direct Memory

The actual bytes consumed by in-use buffers allocated from direct buffer pools.

**Metric name** `reactor.netty.bytebuf allocator.active.direct.memory`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 2. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## Active Heap Memory

The actual bytes consumed by in-use buffers allocated from heap buffer pools.

**Metric name** `reactor.netty.bytebuf allocator.active.heap.memory`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 3. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## Active Streams

The number of the active HTTP/2 streams.

**Metric name** `reactor.netty.connection.provider.active.streams`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.client.Http2ConnectionProviderMeters`.

Table 4. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>name</code> (required)	NAME.

<code>remote.address</code> <i>(required)</i>	Remote address.
---	-----------------

## Chunk Size

The chunk size for an arena.

**Metric name** `reactor.netty.bytebuf allocator.chunk.size`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 5. Low cardinality Keys

Name	Description
<code>id</code> <i>(required)</i>	ID.
<code>type</code> <i>(required)</i>	TYPE.

## Connections Active

The number of http connections, on the server, currently processing requests.

**Metric name** `reactor.netty.http.server.connections.active`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 6. Low cardinality Keys

Name	Description
<code>local.address</code> <i>(required)</i>	Local address.
<code>uri</code> <i>(required)</i>	URI.

## Connections Total

The number of all opened connections on the server.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type**

gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.channel.ChannelMeters`.

Table 7. Low cardinality Keys

Name	Description
<code>local.address</code> (required)	Local address.
<code>uri</code> (required)	URI.

## Connect Time

### Connect metric.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `timer`.

**Metric name** `%s.active` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `long task timer`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.channel.ConnectObservations`.

Table 8. Low cardinality Keys

Name	Description
<code>remote.address</code> (required)	Remote address.
<code>status</code> (required)	STATUS.

Table 9. High cardinality Keys

Name	Description
<code>net.peer.name</code> (required)	Net peer name.

<code>net.peer.port</code> (required)	Net peer port.
<code>reactor.netty.protocol</code> (required)	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> (required)	Reactor Netty status.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always client).

## Data Received

Amount of the data received, in bytes.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `distribution summary` and **base unit** `bytes`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.

Fully qualified name of the enclosing class `reactor.netty.channel.ChannelMeters`.

Table 10. Low cardinality Keys

Name	Description
<code>remote.address</code> (required)	Remote address.
<code>uri</code> (required)	URI.

## Data Sent

Amount of the data sent, in bytes.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `distribution summary` and **base unit** `bytes`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.

Fully qualified name of the enclosing class `reactor.netty.channel.ChannelMeters`.

Table 11. Low cardinality Keys

Name	Description
<code>remote.address</code> (required)	Remote address.



<code>uri</code> (required)	URI.
-----------------------------	------

## Direct Arenas

The number of direct arenas.

**Metric name** `reactor.netty.bytebuf allocator.direct.arenas`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 12. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## Errors Count

Number of errors that occurred.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** counter.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.channel.ChannelMeters`.

Table 13. Low cardinality Keys

Name	Description
<code>remote.address</code> (required)	Remote address.
<code>uri</code> (required)	URI.

## Heap Arenas

The number of heap arenas.

**Metric name** `reactor.netty.bytebuf allocator.heap.arenas`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 14. Low cardinality Keys

Name	Description
<code>id (required)</code>	ID.
<code>type (required)</code>	TYPE.

## Hostname Resolution Time

Hostname resolution metric.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `timer`.

**Metric name** `%s.active` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `long task timer`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.transport.HostnameResolutionObservations`.

Table 15. Low cardinality Keys

Name	Description
<code>remote.address (required)</code>	Remote address.
<code>status (required)</code>	STATUS.

Table 16. High cardinality Keys

Name	Description
<code>net.peer.name (required)</code>	Net peer name.

<code>net.peer.port</code> <i>(required)</i>	Net peer port.
<code>reactor.netty.protocol</code> <i>(required)</i>	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> <i>(required)</i>	Reactor Netty status.
<code>reactor.netty.type</code> <i>(required)</i>	Reactor Netty type (always client).

## Http Client Data Received Time

Time spent in consuming incoming data on the client.

**Metric name** `reactor.netty.http.client.data.received.time`. **Type** `timer`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.client.HttpClientMeters`.

Table 17. Low cardinality Keys

Name	Description
<code>method</code> <i>(required)</i>	METHOD.
<code>remote.address</code> <i>(required)</i>	Remote address.
<code>status</code> <i>(required)</i>	STATUS.
<code>uri</code> <i>(required)</i>	URI.

## Http Client Data Sent Time

Time spent in sending outgoing data from the client.

**Metric name** `reactor.netty.http.client.data.sent.time`. **Type** `timer`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.client.HttpClientMeters`.

Table 18. Low cardinality Keys

Name	Description
<code>method</code> (required)	METHOD.
<code>remote.address</code> (required)	Remote address.
<code>uri</code> (required)	URI.

## Http Client Response Time

Response metric.

**Metric name** `reactor.netty.http.client.response.time`. **Type** timer.

**Metric name** `reactor.netty.http.client.response.time.active`. **Type** long task timer.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.client.HttpClientObservations`.

Table 19. Low cardinality Keys

Name	Description
<code>method</code> (required)	METHOD.
<code>remote.address</code> (required)	Remote address.
<code>status</code> (required)	STATUS.
<code>uri</code> (required)	URI.

Table 20. High cardinality Keys

Name	Description
<code>http.status_code</code> (required)	Status code.

<code>http.url</code> (required)	URL.
<code>net.peer.name</code> (required)	Net peer name.
<code>net.peer.port</code> (required)	Net peer port.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always client).

## Http Server Data Received

Amount of the data received, in bytes.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `distribution summary` and **base unit** `bytes`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 21. Low cardinality Keys

Name	Description
<code>uri</code> (required)	URI.

## Http Server Data Received Time

Time spent in consuming incoming data on the server.

**Metric name** `reactor.netty.http.server.data.received.time`. **Type** `timer`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 22. Low cardinality Keys

Name	Description
<code>method</code> (required)	METHOD.

<code>uri</code> (required)	URI.
-----------------------------	------

## Http Server Data Sent

Amount of the data sent, in bytes.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `distribution summary` and **base unit** `bytes`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 23. Low cardinality Keys

Name	Description
<code>uri</code> (required)	URI.

## Http Server Data Sent Time

Time spent in sending outgoing data from the server.

**Metric name** `reactor.netty.http.server.data.sent.time`. **Type** `timer`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 24. Low cardinality Keys

Name	Description
<code>method</code> (required)	METHOD.
<code>status</code> (required)	STATUS.
<code>uri</code> (required)	URI.

## Http Server Errors Count

Number of errors that occurred.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** `counter`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 25. Low cardinality Keys

Name	Description
<code>uri (required)</code>	URI.

## Http Server Response Time

Response metric.

**Metric name** `reactor.netty.http.server.response.time`. **Type** `timer`.

**Metric name** `reactor.netty.http.server.response.time.active`. **Type** `long task timer`.



KeyValues that are added after starting the Observation might be missing from the `*.active metrics`.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerObservations`.

Table 26. Low cardinality Keys

Name	Description
<code>method (required)</code>	METHOD.
<code>status (required)</code>	STATUS.
<code>uri (required)</code>	URI.

Table 27. High cardinality Keys

Name	Description
------	-------------

<code>http.scheme</code> <i>(required)</i>	HTTP scheme.
<code>http.status_code</code> <i>(required)</i>	Status code.
<code>net.host.name</code> <i>(required)</i>	Net host name.
<code>net.host.port</code> <i>(required)</i>	Net host port.
<code>reactor.netty.type</code> <i>(required)</i>	Reactor Netty type (always server).

## Idle Connections

The number of the idle connections in the connection pool.

**Metric name** `reactor.netty.connection.provider.idle.connections`. **Type** `gauge`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.client.Http2ConnectionProviderMeters`.

Table 28. Low cardinality Keys

Name	Description
<code>id</code> <i>(required)</i>	ID.
<code>name</code> <i>(required)</i>	NAME.
<code>remote.address</code> <i>(required)</i>	Remote address.

## Max Connections

The maximum number of active connections that are allowed in the connection pool.

**Metric name** `reactor.netty.connection.provider.max.connections`. **Type** `gauge`.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.resources.ConnectionProviderMeters`.

Table 29. Low cardinality Keys



Name	Description
<code>id</code> (required)	ID.
<code>name</code> (required)	NAME.
<code>remote.address</code> (required)	Remote address.

## Max Pending Connections

The maximum number of requests that will be queued while waiting for a ready connection from the connection pool.

**Metric name** `reactor.netty.connection.provider.max.pending.connections`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.resources.ConnectionProviderMeters`.

Table 30. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>name</code> (required)	NAME.
<code>remote.address</code> (required)	Remote address.

## Normal Cache Size

The size of the normal cache.

**Metric name** `reactor.netty.bytebuf allocator.normal.cache.size`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 31. Low cardinality Keys

Name	Description
------	-------------

<code>id (required)</code>	ID.
<code>type (required)</code>	TYPE.

## Pending Connections

The number of the request, that are pending acquire a connection from the connection pool.

**Metric name** `reactor.netty.connection.provider.pending.connections`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.resources.ConnectionProviderMeters`.

Table 32. Low cardinality Keys

Name	Description
<code>id (required)</code>	ID.
<code>name (required)</code>	NAME.
<code>remote.address (required)</code>	Remote address.

## Pending Streams

The number of requests that are waiting for opening HTTP/2 stream.

**Metric name** `reactor.netty.connection.provider.pending.streams`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.client.Http2ConnectionProviderMeters`.

Table 33. Low cardinality Keys

Name	Description
<code>id (required)</code>	ID.
<code>name (required)</code>	NAME.

<code>remote.address</code> <i>(required)</i>	Remote address.
---	-----------------

## Pending Tasks

The event loop pending scheduled tasks.

**Metric name** `reactor.netty.eventloop.pending.tasks`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.EventLoopMeters`.

Table 34. Low cardinality Keys

Name	Description
<code>name</code> <i>(required)</i>	NAME.

## Small Cache Size

The size of the small cache.

**Metric name** `reactor.netty.bytebuf allocator.small.cache.size`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 35. Low cardinality Keys

Name	Description
<code>id</code> <i>(required)</i>	ID.
<code>type</code> <i>(required)</i>	TYPE.

## Streams Active

The number of HTTP/2 streams currently active on the server

**Metric name** `reactor.netty.http.server.streams.active`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerMeters`.

Table 36. Low cardinality Keys

Name	Description
<code>local.address</code> (required)	Local address.
<code>uri</code> (required)	URI.

## Thread Local Caches

The number of thread local caches.

**Metric name** `reactor.netty.bytebuf allocator.threadlocal.caches`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 37. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## Tls Handshake Time

TLS handshake metric.

**Metric name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** timer.

**Metric name** `%s.active` - since it contains `%s`, the name is dynamic and will be resolved at runtime. **Type** long task timer.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.



Micrometer internally uses `nanoseconds` for the baseunit. However, each backend determines the actual baseunit. (i.e. Prometheus uses seconds)

Fully qualified name of the enclosing class `reactor.netty.tcp.TlsHandshakeObservations`.

Table 38. Low cardinality Keys

Name	Description
<code>remote.address</code> (required)	Remote address.
<code>status</code> (required)	STATUS.

Table 39. High cardinality Keys

Name	Description
<code>reactor.netty.protocol</code> (required)	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> (required)	Reactor Netty status.
<code>reactor.netty.type</code> (required)	Reactor Netty type (client/server).

## Total Connections

The number of all connections in the connection pool, active or idle.

**Metric name** `reactor.netty.connection.provider.total.connections`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.resources.ConnectionProviderMeters`.

Table 40. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>name</code> (required)	NAME.
<code>remote.address</code> (required)	Remote address.

## Used Direct Memory

The number of bytes reserved by direct buffer allocator.

**Metric name** `reactor.netty.bytebuf.allocator.used.direct.memory`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 41. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## Used Heap Memory

The number of bytes reserved by heap buffer allocator.

**Metric name** `reactor.netty.bytebuf.allocator.used.heap.memory`. **Type** gauge.



KeyValues that are added after starting the Observation might be missing from the \*.active metrics.

Fully qualified name of the enclosing class `reactor.netty.transport.ByteBufAllocatorMeters`.

Table 42. Low cardinality Keys

Name	Description
<code>id</code> (required)	ID.
<code>type</code> (required)	TYPE.

## B.1.2. Observability - Spans

Below you can find a list of all spans declared by this project.

### Connect Span

Connect Span.

**Span name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime.

Fully qualified name of the enclosing class `reactor.netty.channel.ConnectSpans`.

Table 43. Tag Keys

Name	Description
------	-------------

<code>net.peer.name</code> (required)	Net peer name.
<code>net.peer.port</code> (required)	Net peer port.
<code>reactor.netty.protocol</code> (required)	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> (required)	Reactor Netty status.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always client).

## Hostname Resolution Span

Hostname Resolution Span.

**Span name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime.

Fully qualified name of the enclosing class `reactor.netty.transport.HostnameResolutionSpans`.

Table 44. Tag Keys

Name	Description
<code>net.peer.name</code> (required)	Net peer name.
<code>net.peer.port</code> (required)	Net peer port.
<code>reactor.netty.protocol</code> (required)	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> (required)	Reactor Netty status.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always client).

## Http Client Response Span

Response Span.

**Span name** `%s` - since it contains `%s`, the name is dynamic and will be resolved at runtime.

Fully qualified name of the enclosing class `reactor.netty.http.client.HttpClientSpans`.

Table 45. Tag Keys

Name	Description
<code>http.status_code</code> (required)	Status code.
<code>http.url</code> (required)	URL.
<code>net.peer.name</code> (required)	Net peer name.
<code>net.peer.port</code> (required)	Net peer port.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always client).

## Http Server Response Span

Response Span.

**Span name %s** - since it contains %s, the name is dynamic and will be resolved at runtime.

Fully qualified name of the enclosing class `reactor.netty.http.server.HttpServerSpans`.

Table 46. Tag Keys

Name	Description
<code>http.scheme</code> (required)	HTTP scheme.
<code>http.status_code</code> (required)	Status code.
<code>net.host.name</code> (required)	Net host name.
<code>net.host.port</code> (required)	Net host port.
<code>reactor.netty.type</code> (required)	Reactor Netty type (always server).

## Tls Handshake Span

TLS Handshake Span.

**Span name %s** - since it contains %s, the name is dynamic and will be resolved at runtime.

Fully qualified name of the enclosing class `reactor.netty.tcp.TlsHandshakeSpans`.

Table 47. Tag Keys

Name	Description
<code>reactor.netty.protocol</code> (required)	Reactor Netty protocol (tcp/http etc.).
<code>reactor.netty.status</code> (required)	Reactor Netty status.
<code>reactor.netty.type</code> (required)	Reactor Netty type (client/server).
<code>remote.address</code> (required)	Remote address.